


# IBM Business Process Manager V8.0 Performance Tuning and Best Practices



Redpaper



## International Technical Support Organization

# IBM Business Process Manager V8.0 Performance Tuning and Best Practices

April 2013

<b>Note:</b> Before using this information and the product it supports, read the information in "Notices" on page vii.
First Edition (April 2012)
First Edition (April 2013)
This edition applies to IBM Business Process Manager V8.0, IBM Integration Designer V8.0, and IBM Business Monitor V8.0.

# **Contents**

Notices	
Preface	ix
Comments welcome	x
Chapter 1. Overview	2
Chapter 2. Architecture best practices  2.1 Top tuning and deployment guidelines  2.2 Modeling and developing applications  2.2.1 Common best practices  2.2.2 Process Designer architecture best practices  2.2.3 Integration Designer best practices.	6 7 8
2.3 Topology 2.3.1 Deploy appropriate hardware 2.3.2 Deploy local modules in the same server	. 13 . 13 . 14
2.3.3 Best practices for clustering	. 15 . 16
2.4.2 Use a high-performing browser.  2.4.3 Enable browser caching.  2.4.4 Locate servers physically near clients, and databases physically near servers.	. 18 . 18
2.4.5 Use modern desktop hardware	. 18 . 19
2.5.2 Large object design patterns.  2.5.3 Data management  2.6 Considerations for 64-bit mode  2.7 Business Monitor.	. 20 . 21
2.7.1 Event processing 2.7.2 Dashboard 2.7.3 Database server	. 22 . 22
Chapter 3. Development best practices	. 24
<ul> <li>3.1.1 Clear variables in exposed human services that are not intended to end</li> <li>3.1.2 Do not use multi-instance loops in the system lane or for batch activities</li> <li>3.1.3 Use conditional joins only when necessary</li> <li>3.1.4 Guidelines for error handling</li> </ul>	. 24 . 25
3.1.5 Use sequential system lane activities efficiently	. 26 . 27

4.7.2 Tuning for large objects	63
4.7.3 Tuning for maximum concurrency	64
4.7.4 Messaging tuning	67
4.7.5 Clustered topology tuning	. 70
4.7.6 Web services tuning	. 70
4.7.7 Tuning Human Workflow for Business Space	. 71
4.7.8 Power management tuning	. 72
4.7.9 Setting AIX threading parameters	. 72
4.8 Tuning for Business Process Execution Language business processes	. 73
4.8.1 Tuning Work Manager-based navigation for business processes	. 73
4.8.2 Tuning the business process container for Java Message Service navigation	
4.8.3 Tuning task list and process list queries	. 74
4.8.4 Tuning Business Process Choreographer API calls	. 74
4.8.5 Tuning intermediate components for concurrency	
4.9 Mediation flow component tuning	
4.9.1 Tuning the database if using persistent messaging	
4.9.2 Disabling event distribution for Common Event Infrastructure	
4.9.3 Configuring WebSphere Service Registry and Repository cache timeout	
4.10 Business Monitor tuning	
4.10.1 Configuring Java heap sizes	
4.10.2 Configuring Common Event Infrastructure	
4.10.3 Configuring message consumption batch size	
4.10.4 Enabling key performance indicator caching	
4.10.5 Using table-based event delivery	
4.10.6 Enabling the Data Movement Service	
4.11 Enable browser caching	
4.11.1 Ensuring browser cache is enabled in Internet Explorer	
4.11.2 Ensuring browser cache is enabled in Firefox	
4.112 Tuning the HTTP server	
4.13 General database tuning	
4.13.1 Providing adequate statistics for optimization	
4.13.2 Placing database log files on a fast disk subsystem	
4.13.3 Placing logs on a separate device from the table space containers	
4.13.4 Providing sufficient physical memory	
4.13.5 Avoiding double buffering	
4.13.6 Refining table indexes as required	
4.13.7 Archiving completed process instances	
4.14 DB2-specific database tuning	
· ·	
4.14.2 Setting buffer pool sizes correctly	
4.14.3 Maintaining correct table indexing	
4.14.4 Sizing log files appropriately	
4.14.5 Using System Managed Storage for table spaces that contains LOBs	
4.14.6 Ensuring sufficient locking resources are available	
4.14.7 Setting boundaries on the size of the catalog cache for clustered applications .	
4.14.8 Sizing the database heap appropriately before DB2 9.5	
4.14.9 Sizing the log buffer appropriately before DB2 9.7	
4.14.10 Tuning for BPEL business processes	
4.14.11 Suggestions for Business Monitor	
4.15 Oracle-specific database tuning	
4.15.1 Updating database statistics	
4.15.2 Correctly setting buffer cache sizes	
4.15.3 Maintaining correct table indexing	89

4.15.4 Sizing log files appropriately894.15.5 Using the Oracle SQL Tuning Advisor for long running SQL statements894.15.6 File system tuning894.15.7 Creating table spaces894.15.8 Special considerations for large objects (LOBs)904.15.9 Setting prepared statement cache size90
4.15.10 Specific tuning parameter recommendations
4.15.11 Suggestions for Business Process Execution Language business processes . 91 l.16 Advanced Java heap tuning
4.16.1 Monitoring garbage collection
4.16.2 Setting the heap size for most configurations
4.16.3 Setting the heap size when running multiple JVMs on one system
4.16.4 Reducing or increasing heap size if OutOfMemory errors occur 94
1.17 Tuning for WebSphere InterChange Server migrated workloads
Chapter 5. Initial configuration settings
5.1 Business Process Manager server settings
5.1.1 Three-tiered: Using BPEL business processes with web services and remote DB2
system
5.1.2 Three-tiered: Using Human Services with BPMN business processes
5.1.3 Two-tiered: Using file store for Java Message Service
5.2 Mediation Flow Component settings
5.2.2 Mediation Flow Component settings for web services
5.2.3 Mediation Flow Component settings for Java Message Service
5.2.4 DB2 settings for Java Message Service persistent
Related publications
BM Redbooks
Online resources
How to get Redbooks
Join from IPM

### **Notices**

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing, IBM Corporation, North Castle Drive, Armonk, NY 10504-1785 U.S.A.

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### **COPYRIGHT LICENSE:**

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs.

#### **Trademarks**

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corporation in the United States, other countries, or both. These and other IBM trademarked terms are marked on their first occurrence in this information with the appropriate symbol (® or ™), indicating US registered or common law trademarks owned by IBM at the time this information was published. Such trademarks may also be registered or common law trademarks in other countries. A current list of IBM trademarks is available on the Web at http://www.ibm.com/legal/copytrade.shtml

The following terms are trademarks of the International Business Machines Corporation in the United States, other countries, or both:

AIX® IBM®
alphaWorks® IMS™
CICS® MQSeries®
Cognos® POWER6®
DB2® Redbooks®
developerWorks® Redpaper™

The following terms are trademarks of other companies:

Intel, Intel logo, Intel Inside logo, and Intel Centrino logo are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Windows, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

Java, and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, or service names may be trademarks or service marks of others.

## **Preface**

This IBM® Redpaper™ publication provides performance tuning tips and best practices for IBM Business Process Manager V8.0 (all editions) and IBM Business Monitor V8.0. These products represent an integrated development and runtime environment based on a key set of service-oriented architecture (SOA) and business process management technologies. Such technologies include Service Component Architecture (SCA), Service Data Object (SDO), Business Process Execution Language (BPEL) for web services, and Business Processing Modeling Notation (BPMN).

Both IBM Business Process Manager and Business Monitor build on the core capabilities of the IBM WebSphere® Application Server infrastructure. As a result, Business Process Manager solutions benefit from tuning, configuration, and best practices information for WebSphere Application Server and the corresponding platform Java virtual machines (JVMs).

This paper targets a wide variety of groups, both within IBM (development, services, technical sales, and others) and customers. For customers who are either considering or are in the early stages of implementing a solution incorporating Business Process Manager and Business Monitor, this document proves a useful reference. The paper is useful both in terms of best practices during application development and deployment and as a reference for setup, tuning, and configuration information.

This paper introduces many issues that influence performance of each product and can serve as a guide for making rational first choices in terms of configuration and performance settings. Similarly, customers who already implemented a solution with these products might use the information presented here to gain insight into how their overall integrated solution performance might be improved.

#### The team who wrote this paper

This paper is authored by the Business Process Manager performance team, with members in Austin, Texas; Böblingen, Germany; Hursley, England; and Raleigh, North Carolina.

- ▶ John Alcorn
- ▶ Mike Collins
- Gudrun Eckl-Regenhardt
- Weiming Gu
- ► Paul Harris
- ► Ben Hoflich
- Kean Kuiper
- Sam Massey
- ► Stuart McKnight
- ► Ali Moghadam
- Rachel Norris
- ► Chris Richardson
- Martin Ross
- ► Randall Theobald

#### Now you can become a published author, too!

Here's an opportunity to spotlight your skills, grow your career, and become a published author - all at the same time! Join an ITSO residency project and help write a book in your area of expertise, while honing your experience using leading-edge technologies. Your efforts will help to increase product acceptance and customer satisfaction, as you expand your network of technical contacts and relationships. Residencies run from two to six weeks in length, and you can participate either in person or as a remote resident working from your home base.

Find out more about the residency program, browse the residency index, and apply online at:

ibm.com/redbooks/residencies.html

#### **Comments welcome**

Your comments are important to us!

We want our papers to be as helpful as possible. Send us your comments about this paper or other IBM Redbooks® publications in one of the following ways:

▶ Use the online **Contact us** review Redbooks form found at:

ibm.com/redbooks

► Send your comments in an email to:

redbooks@us.ibm.com

Mail your comments to:

IBM Corporation, International Technical Support Organization Dept. HYTD Mail Station P099 2455 South Road Poughkeepsie, NY 12601-5400

#### Stay connected to IBM Redbooks

▶ Find us on Facebook:

http://www.facebook.com/pages/IBM-Redbooks/178023492563?ref=ts

► Follow us on Twitter:

http://twitter.com/ibmredbooks

► Look for us on LinkedIn:

http://www.linkedin.com/groups?home=&gid=2130806

► Explore new Redbooks publications, residencies, and workshops with the IBM Redbooks weekly newsletter:

https://www.redbooks.ibm.com/Redbooks.nsf/subscribe?OpenForm

▶ Stay current on recent Redbooks publications with RSS Feeds:

http://www.redbooks.ibm.com/rss.html



# 1

# **Overview**

This chapter introduces the products that this paper covers, and the overall document structure.

#### 1.1 Products covered in this publication

This paper describes the following products:

► IBM Business Process Manager V8.0. (all editions)

This product combines simplicity, ease-of-use, and task-management capabilities that support enterprise integration and transaction process management requirements as part of an overall SOA solution. Business Process Manager adds value in the following ways:

- Optimizes business processes by providing visibility to all process participants, fostering greater collaboration and enabling continuous process improvement across distributed platforms and IBM z/OS®.
- Increases efficiency with a federated view for performing tasks, managing work items, tracking performance, and responding to events, all in real time.
- Empowers users with real-time analytics to optimize business processes.
- Enhances time-to-value through business user-focused design capabilities, including process coaching to guide users easily through the steps of a process.
- Confidently manages change with a unified model-driven environment that makes the same process version visible to everybody.
- Combines simplicity, ease-of-use, and task management capabilities for IBM WebSphere Lombardi Edition with key capabilities from IBM WebSphere Process Server (Advanced Edition only). These capabilities support enterprise integration and transaction process management requirements as part of an overall SOA.
- Offers compatibility with earlier versions for the latest versions of WebSphere Process Server (Advanced Edition only) and WebSphere Lombardi Edition.

#### ► IBM Business Monitor V8.0

This product provides comprehensive business activity monitoring (BAM). This feature enables user visibility into real-time, end-to-end business operations, transactions, and processes to help optimize processes and increase efficiency. Business Monitor adds value in the following ways:

- Provides a high-performance BAM solution for processes and applications running in disparate environments which might or might not be implemented using any Business Process Manager technology.
- Offers built-in tools and runtime support for integrated BAM for Business Process Manager.
- Integrates IBM Cognos® Business Intelligence Server V10.1.1 for advanced analysis and reporting on historical data.
- Automatically generates dashboards for your Business Process Modeling Notation V2.0 (BPMN2) processes. This feature allows real-time visibility to process instances, key performance indicators (KPIs), Cognos reports, and annotated BPMN2 process diagrams.
- Includes fine-grained security to enable or prevent anyone from seeing a wide range of information depth or detail.
- Enables enhanced business user customization of data filtering and dashboard controls and reports.
- Enables views of KPIs, metrics, and alerts through web interfaces, Apple iPad, mobile devices, and corporate portals.
- Is available for distributed platform and z/OS.

#### 1.2 Publication structure

The following list summarizes each chapter of this document:

Chapter 1, "Overview" on page 1

This current chapter presents the scope of the content of this paper.

► Chapter 2, "Architecture best practices" on page 5

This chapter provides guidance for architecture and topology decisions that produce well-performing and scalable Business Process Manager solutions.

► Chapter 3, "Development best practices" on page 23

This chapter presents guidelines for solution developers that lead to high-performing systems.

► Chapter 4, "Performance tuning and configuration" on page 47

This chapter explains the tuning methodology and configuration parameters and settings to optimize the major components in a Business Process Manager solution.

► Chapter 5, "Initial configuration settings" on page 97

This chapter provides details about the software configurations, including specific parameter settings, used for representative workloads that are evaluated by the IBM performance team during the development of IBM Business Process Manager and Business Monitor.

"Related publications" on page 107

This chapter provides links to best practices, performance information, and product information for both the products described in this publication and related products such as WebSphere Application Server, IBM DB2®, and other applications.



# **Architecture best practices**

This chapter provides guidance for how to design a high-performing and scalable Business Process Manager solution. The purpose of this chapter is to highlight the best practices that are associated specifically with the technologies and features that are delivered in the Business Process Manager and Business Monitor products covered in this paper. However, these products are based on existing technologies (such as WebSphere Application Server and DB2). Each of these technologies has its own associated best practices.

This paper does not enumerate these best practices outside Business Process Manager. See "Related publications" on page 107 for reference information and links to these other technologies.

#### 2.1 Top tuning and deployment guidelines

This chapter details architectural best practices for Business Process Manager V8.0 solutions. Development best practices and performance tuning and configuration are covered in subsequent chapters.

If you read nothing else in this document, read and adhere to the following key tuning and deployment guidelines. They are relevant in virtually all performance-sensitive deployments:

- ▶ Use high-performance disk subsystems. In virtually any realistic topology, you must have a server-class disk subsystem (for example, a RAID adapter with multiple physical disks) on the tiers that host the Business Process Manager and Business Monitor data stores to achieve acceptable performance. This guidance applies to all databases (Process Server, Process Center, Message Engine, Business Monitor, and others), and the Business Process Manager Process Server cluster members also. We cannot overstate this point. In many cases, performance is improved by several factors by using appropriate disk subsystems.
- Use the most current Business Process Manager and Business Monitor release, with the most current fix pack. IBM improves the performance, scalability, serviceability, and quality of the Business Process Manager product line with every release and fix pack. With the most current level, you can avoid encountering issues that were already resolved by IBM.
- ► Set an appropriate Java heap size to deliver optimal throughput and response time. Memory usage data that is obtained through the JVM's verbose garbage collection option (verbosegc) helps determine the optimal settings. Further information is available in 4.3.2, "Java memory management tuning parameters" on page 53.
- ► Tune your database for optimal performance. Correct tuning and deployment choices for databases can greatly increase overall system throughput. For example, set the buffer pool or cache size to a minimum of 2 GB. For more details, see 4.13, "General database tuning" on page 80, and either 4.14, "DB2-specific database tuning" on page 82 or 4.15, "Oracle-specific database tuning" on page 88
- ▶ Disable tracing and logging. Tracing and logging are important when debugging, but the resources to do so severely affects performance. More information is available in 4.7.1, "Tracing and monitoring considerations" on page 62.
- Configure thread pools to enable sufficient concurrency. This configuration is important for high-volume, highly concurrent workloads because the thread pool settings directly influence how much work the server can concurrently processes. For more information, see "Configuring thread pool sizes" on page 65.
- ► Use fast, high bandwidth network connections. There is significant network activity for many Business Process Manager activities, so minimizing network latency and ensuring sufficient bandwidth is essential between the following items:
  - Process Designer and Process Center
  - Process Center and its database
  - Process Center and online Process Servers
  - Process Portal and Process Server
  - Process Server and its databases
- ► For business processes that use Business Process Modeling Notation (BPMN), tune the bpd-queue-capacity and max-thread-pool-size parameters to achieve optimal throughput and scaling. For more information, see 4.5.2, "Tune the Event Manager" on page 58.

- ► For business processes that use Business Process Execution Language (BPEL), follow these guidelines:
  - Where possible, use non-interruptible processes (also known as microflows or short-running processes) instead of long-running processes (also known as macroflows or long-running processes). Many processes need macroflows (for example, if human tasks are employed or a state must be persisted). However, a significant amount of performance resources is associated with macroflows. If some portion of the solution requires macroflows, separate the solution into both microflows and macroflows to maximize use of microflows. For details, see "Choose microflows where possible" on page 11.
  - For task and process list queries, use composite query tables. Query tables are designed to produce excellent response times for high-volume task and process list queries. For details, see "Choose query tables for task list and process list queries" on page 11.
  - Use Work Manager-based navigation to improve throughput for long-running processes. This optimization reduces the number of allocated objects, the number of retrieved objects that are from the database, and the number of messages sent for Business Process Choreographer messaging. For more information, see 4.8.1, "Tuning Work Manager-based navigation for business processes" on page 73.
  - Avoid using asynchronous invocations unnecessarily. Synchronous invocation is often needed on the edges of modules, but not within a module. Use synchronous preferred interaction styles, as described in "Setting the Preferred Interaction Style to Synchronous when possible" on page 40.
  - Avoid overly granular transaction boundaries in Service Component Architecture (SCA) and BPEL. Every transaction commit results in expensive database and messaging operations. Design your transactions carefully, as described in 3.2.9, "Transactional considerations" on page 38.

#### 2.2 Modeling and developing applications

This section describes best practices for modeling and developing Business Process Manager applications. Business Process Manager V8.0 Advanced Edition offers two authoring environments:

- ► Process Designer is used to model, develop, and deploy Business Processing Modeling Notation (BPMN) business processes, which often involve human interactions. The Process Designer is the only authoring tool for Business Process Manager V8.0 Standard Edition.
- ► Integration Designer is used to build and implement services that are automated or start other services. These services include web services, enterprise resource applications, or applications that run in IBM CICS® and IBM IMS™, which exist in the enterprise. Integration Designer is also the tool to use for authoring BPEL business processes.

These authoring environments both interact with the *Process Center*, which is a shared repository and runtime environment.

Two individuals with the following separate roles with skill sets work together to develop business process management applications by using these environments:

- ► The *business author* is responsible for authoring all business processes. The business author is able to use services but is not interested in the implementation details or how they work. The business author uses Process Designer to create business process diagrams (BPDs) that optionally use advanced integration services (AISs).
- ► The *integration programmer* is responsible for doing all of the integration work necessary to support the processes that the business author creates. For example, the integration programmer implements all the AISs and produces mappings between back-end formats and the requirements of current applications. The integration programmer uses Integration Designer.

The remainder of this section is organized based on user type, with separate sections describing common best practices and best practices for Process Designer (for business authors) and Integration Designer (for integration programmers).

#### 2.2.1 Common best practices

This section outlines general guidelines for designing and configuring elements of Business Process Manager V8.0.

#### Choose the appropriate granularity for a process

A business process and its individual steps should have business significance and not try to mimic programming-level granularity. Use programming techniques such as plain old Java objects (POJOs) or Java snippets for logic without business significance. This material is explained further in the IBM developerWorks® article "Software components: Coarse-grained versus fine-grained," available at the following website:

http://www.ibm.com/developerworks/webservices/library/ws-soa-granularity/

#### Use events judiciously

The purpose of event emission in Business Process Manager V8.0 is business activity monitoring. Because event emission uses a persistent mechanism, it can consume significant processor resources. Use Common Base Events for events that have business relevance only. Do not confuse business activity monitoring and IT monitoring. The Performance Monitoring Infrastructure (PMI) is far more appropriate for IT monitoring.

The following principles generally apply for most customers:

- ► Customers are concerned about the state of their business and their processes. Therefore, events that signify changes in state are important. For long-running and human activities, this change in state is fairly common. Use events to track when long-running activities complete, such as when tasks change state.
- ► For short-running flows that complete within seconds, it is sufficient to know that a flow completes, perhaps with the associated data. Distinguishing events within a microflow or general system service that are only milliseconds or seconds apart usually does not make sense. Therefore, two events (start and end) are sufficient for a microflow or straight through process.

#### 2.2.2 Process Designer architecture best practices

This section presents best practices for the Process Designer.

#### **Use a fast connection between Process Designer and Process Center**

The Process Designer interacts frequently with the Process Center for authoring tasks. For this reason, minimize network latency to provide optimal response times. Place the Process Center in the same physical location as the Process Designer users. Also, place the Process Center in the same physical location as its database. If you cannot relocate the Process Center, you can remotely connect to the environment where the Process Center is physically located and use the Process Designer through that mechanism.

#### Minimize use of Service Tasks

Where possible, call system lane tasks with Service No Task because Service Tasks have significant performance costs. The potential performance benefit of executing Service Tasks asynchronously is usually far outweighed by the additional overhead of Service Tasks, because the Process Server persists the state and context to the database at transition points. In particular, avoid patterns such as the following pattern:

```
JavaScript 1 \rightarrow Service Task 1 \rightarrow JavaScript 2 \rightarrow Service Task 2
```

If possible, avoid Service Tasks altogether, or switch to the following example to minimize the number of times that state and context are persisted:

JavaScript 1  $\rightarrow$  JavaScript 2  $\rightarrow$  Service Tasks 1 and 2 combined

#### Use searchable business variables judiciously

Business variables add more overhead to the Process Server, so limit business data searches to only those fields that need to be searchable in the Process Portal. As a general guideline, rarely are more than 10 searchable variables required in a BPD. If your implementation has more searchable variables than this, re-evaluate your design and re-factor as needed to reduce the number of searchable variables.

#### Manage variable usage

Variables are persisted to the database when execution contexts are saved, which happens fairly frequently (for example, when changing from BPD to service execution, and when running each coach). These persistence operations are expensive. Minimize the persistence cost in the following ways:

- Minimize the number of variables used.
- ► Minimize the size of each variable.
- ► Set variables, such as DB result sets, to null when they are no longer needed.
- ▶ Minimize the number and size of variables that are passed to each task.
- ▶ If industry-standard schema are being used (for example, ACORD or HIPAA), recognize that these schema contain many fields, and use only the variables that are required from the schema. If necessary, convert to or from the industry standard schema on the edges of the application to avoid unnecessary persistence cost in the BPD processing.

#### Turn off auto-tracking in business process diagrams if not required

Auto-tracking is enabled by default for BPDs. This capability is important for many BPDs because it enables the gathering, tracking, and reporting of key business metrics. However, an additional cost exists as a result of auto-tracking because the events are processed by the Performance Data Warehouse and persisted in the database. Disable auto tracking for BPDs that do not require tracking and reporting business metrics.

Also consider creating tracking groups to only track key business events, and then disable auto-tracking. This will ensure that the events persisted are only those required for business metrics.

#### Avoid business process diagrams (BPDs) that run perpetually

Some BPDs run forever. Although certain business processes must run perpetually, design this type of BPD only if the capability is strictly required. BPDs that run perpetually continually poll for new events, which uses server processor resources. Consider using other communication mechanisms (such as Java Message Service queues) instead of polling. If polling is necessary, use an undercover agent (UCA) instead of a BPD to do the polling. Also, disable auto-tracking for these BPDs to avoid excessive traffic to the Performance Data Warehouse.

#### **Develop efficient coaches**

To develop well-performing coaches, consider the following guidelines:

- ► Use custom visibility sparingly.
- ► Avoid large, complex coaches.
- ► Avoid large, repeating tables. Page the results instead.
- Always wire coaches to end nodes.

#### Minimize use of large JavaScript scripts

Avoid large JavaScript blocks because JavaScript is interpreted and therefore is slower to process than other compiled mechanisms such as Java code. Large JavaScript blocks can also produce very large Document Object Model (DOM) trees, which are expensive for browsers to process and render. Finally, large JavaScript blocks are often indicative of too much logic being placed in the Business Process Manager layer.

As a general guideline, limit a JavaScript block to 50 lines. If your implementation exceeds this value, re-evaluate the design and re-factor the implementation to use smaller JavaScript blocks.

#### Avoid direct SQL access to internal Business Process Manager tables

SQL tools provide the capability to access any database table, including internal Business Process Manager tables such as LSW\_TASK, LSW\_PROCESS, and so on. Avoid accessing internal Business Process Manager tables directly, because these are internal tables and the definition and content of the tables may change in future Business Process Manager releases. Instead, use published Business Process Manager APIs, such as JavaScript and REST APIs.

It is also important to avoid storing internal Business Process Manager information in application-specific persistent storage, because it is difficult to maintain consistency between the internal Business Process Manager persistent storage and the application's own persistent storage.

#### 2.2.3 Integration Designer best practices

This section describes best practices for using Integration Designer.

#### Choose microflows where possible

Use macroflows only where required (for example, for long-running service invocations and human tasks). Microflows exhibit significantly improved performance at run time. A non-interruptible microflow instance is run in one J2EE transaction with no persistence of state. However, an interruptible macroflow instance is typically run in several J2EE transactions, requiring that state persist in a database at transaction boundaries.

Where possible, use synchronous interactions for non-interruptible processes. A non-interruptible process is more efficient than an interruptible process because it does not use state or persistence in the backing database system.

To determine whether a process is interruptible, in the Integration Designer, click  $Properties \rightarrow Details$ . A process is interruptible if the Process is long-running check box is selected.

If interruptible processes are required for some capabilities, separate the processes so that non-interruptible processes can handle the most frequent scenarios and interruptible processes handle exceptional cases.

#### Choose query tables for task list and process list queries

Query tables are designed to provide good response times for high-volume task lists and process list queries. Query tables offer improved query performance in the following ways:

- ► Improved access to work items, reducing the complexity of the database query
- ► Configurable high-performance filters for tasks, process instances, and work items
- Composite query tables to bypass authorization through work items.
- Composite query tables that allow query table definitions reflecting information shown in task lists and process lists

For more information, see the following references:

- ► PA71: Business Process Manager Advanced Query Table Builder http://www.ibm.com/support/docview.wss?uid=swg24021440
- Query tables in Business Process Choreographer in the IBM Business Process Manager
   8.0 Information Center

http://pic.dhe.ibm.com/infocenter/dmndhelp/v8r0mx/index.jsp?topic=%2Fcom.ibm.wbpm.bpc.doc%2Ftopics%2Fc6bpel querytables composit.html

#### Choose efficient metadata management

This section describes best practices for metadata usage.

#### Follow Java language specification for complex data type names

Business Process Manager Advanced Edition allows characters in business object (BO) type names that are permissible in Java class names, the underscore (\_) character, for example. However, the internal data representation of complex data type names uses Java types. As such, performance is better if BO types follow the Java naming standards because valid Java naming syntax requires no additional translation.

#### Avoid use of anonymous derived types in XML schema definitions

Some XML Schema Definition (XSD) features (restrictions on the primitive string type, for example) result in modifications to the type that require a new subtype to be generated. If these types are not explicitly declared, a new subtype (a derived type) is generated at run time. Performance is generally better if this situation can be avoided. Avoid adding restrictions to elements of primitive type where possible. If a restriction is unavoidable, consider creating a new, concrete SimpleType that extends the primitive type to include the restriction. Then XSD elements might use that type without degraded performance.

#### Avoid references to elements in one XML schema definition from another

Avoid referencing an element in one XSD from another. For example, if A.xsd defines an element, AElement (shown in Example 2-1), it might be referenced from another file, B.xsd (shown in Example 2-2).

#### Example 2-1 AElement XSD

#### Example 2-2 AElement referenced from another file

```
<xs:element ref="AElement" min0ccurs="0" />
```

This practice often performs poorly. It is better to define the type concretely and make any new elements use this type. Thus, A.xsd takes the form shown in Example 2-3.

#### Example 2-3 AElementType XSD

The form that B.xsd takes is shown in Example 2-4.

#### Example 2-4 BElement XSD

```
<xs:element name="BElement" type="AElementType" minOccurs="0" />
```

#### Reuse data object type metadata where possible

Within application code, it is common to refer to types, for example, when creating a BO. It is possible to refer to a BO type by name, for example in the method DataFactory.create(String URI, String typeName).

You can also refer to the type by a direct reference, such as in the method DataFactory.create(Type type). In cases where a type is likely to be used more than once, it is faster to retain the type, for example, through DataObject.getType(), and reuse that type for future use.

#### Choose between business state machines and business processes

Business state machines (BSMs) provide an attractive way of implementing business flow logic. For some applications, it is more intuitive to model the business logic as a state machine, making the resultant artifacts easier to understand. However, a BSM is implemented using the business process infrastructure, so there is always a performance impact when choosing BSM over business processes.

If an application can be modeled using either BSM or business processes, and performance is a differentiating factor, choose business processes. Also, more options are available for optimizing business process performance than for BSM performance.

#### Minimize state transitions in business state machines

Where possible, minimize external events to drive state transitions in BSMs. External event-driven state transitions are costly from a performance perspective. In fact, the total time it takes to run a BSM is proportional to the number of state transitions that occur during the life span of the BSM.

For example, if a state machine transitions through states  $A \to B \to B \to B \to C$  (four transitions), making transitions through states  $A \to B \to C$  (two transitions) is twice as time-consuming. Also, automatic state transitions are much less costly than event-driven state transitions. Consider these principles when designing a BSM.

#### 2.3 Topology

In this section, we provide information about choosing an appropriate topology for your solution.

#### 2.3.1 Deploy appropriate hardware

It is important to pick a hardware configuration that contains the resources necessary to achieve high performance in a Business Process Manager environment. The following factors are key considerations in picking a hardware configuration:

#### Processor Cores

Ensure that Business Process Manager servers (Process Servers and Process Centers) are installed on a modern server system with multiple processor cores. Business Process Manager scales well, both for single JVM servers through symmetric multiprocessing (SMP) scaling, and horizontally through clustering.

#### Memory

Business Process Manager servers benefit from both a robust memory subsystem and an ample amount of physical memory. Ensure that the chosen system has server-class memory controllers and as large as possible L2 and L3 caches (optimally, use a system with at least a 4 MB L3 cache). Make sure that there is enough physical memory for all the combined applications (JVMs) that are expected to run concurrently on the system. For 64-bit JVMs (the recommended configuration), 4 GB per JVM is needed if the maximum heap size is 3 GB or less. Add additional physical memory for heap sizes larger than 3 GB. When using a 32-bit JVM, a rough guideline is 2 GB per JVM instance.

#### ▶ Disk

Ensure that the systems hosting the message and data stores (The Process Server nodes, and the database tiers), and also the Process Server and Process Center cluster members, have fast storage. Fast storage typically means using Redundant Array of

Independent Disks (RAID) adapters with writeback caches and disk arrays with many physical drives.

#### ► Network

Ensure that the network is fast enough not to create a system bottleneck. For example, a dedicated 1 or 10 Gigabit Ethernet network is a good choice. Also, minimize latency across the topology (for example, between Process Designer and Process Center, between Process Center and the Process Center database, between Process Portal and Process Server, and between Process Server and the Process Server databases). Techniques to minimize network latency include physical co-location of hardware, and minimizing firewall separation between Business Process Manager components.

#### ▶ Virtualization

When using virtualization such as IBM AIX® dynamic logical partitioning or VMware virtual machines, ensure sufficient physical processor, memory, and I/O resources are allocated to each virtual machine or logical partition (LPAR). Avoid over-committing resources.

#### 2.3.2 Deploy local modules in the same server

If you plan to deploy modules on the same physical server, you can achieve better performance by deploying the modules to the same application server JVM. The server can then take advantage of this locality.

#### 2.3.3 Best practices for clustering

See IBM Redbooks publication *IBM Business Process Manager V7.5 Production Topologies*, SG24-7976, for information about best practices for clustering. This book provides comprehensive guidance on selecting appropriate topologies for both scalability and high availability. Although the document was written for Business Process Manager V7.5, most of the guidance still applies for Business Process Manager 8.0. You can retrieve this document from the following location:

http://www.redbooks.ibm.com/redbooks/pdfs/sg247976.pdf

It is not the intent of this section to repeat content from that book. Rather, this paper distills some of the key considerations when scaling up a topology for maximum performance.

#### Use the remote messaging and remote support deployment pattern

Use the remote messaging and remote support deployment environment pattern for maximum flexibility in scaling. For more information, see the section "Topologies and Deployment environment patterns" in the *IBM Business Process Manager Advanced Installation Guide* at the following location:

 $\label{limits} ftp://ftp.software.ibm.com/software/integration/business-process-manager/library/imuc\_ebpm\_dist\_pdf.pdf$ 

This topology (formerly known as the "Gold Topology") prescribes the use of separate clusters for applications and messaging engines. The topology also prescribes how clusters are used for support applications servers (such as the Common Event Infrastructure (CEI) server or the Business Rules Manager). This topology allows independent control of resources to support the load on each of these elements of the infrastructure.

**Flexibility and cost:** As with many system choices, flexibility comes with some costs. For example, synchronous event emission between an application and the CEI server in this topology is a remote call, which is heavier than a local call. The benefit of this configuration is the independent ability to scale the application and support cluster. We assume that the reader is familiar with these kinds of system tradeoffs as they occur in most server middleware.

#### **Evaluate single server versus clustered topology**

In general, there are three primary issues to consider when evaluating whether to utilize a clustered topology instead of a single server configuration:

- Scalability and load balancing to improve overall performance and throughput
- ► The ability to expand a configuration over time by adding additional cluster members as additional applications are deployed, or additional users are added to the system.
- ► High availability by using failover to another cluster member to prevent loss of service because of hardware or software failures

Although not mutually exclusive, each requires certain considerations. This paper focuses on the performance (throughput) aspects of clustering and not on the high availability aspects.

As a guideline, use a clustered topology for all the reasons noted previously, with a minimum of two cluster members and a minimum of two processor cores per cluster member. This configuration delivers high availability and ensures that a processor-intensive task that consumes significant CPU is less likely to impact other user's response times. This general guideline applies to both Process Server and Process Center. As always, contact IBM TechLine or your IBM Sales Representative to define the specific configuration for your requirements.

#### 2.3.4 Evaluate service providers and external interfaces

One typical usage pattern for Business Process Manager V8.0 is as an integration layer between incoming requests and back-end systems for the business (target applications or service providers). In these scenarios, the throughput is limited by the layer with the lowest throughput capacity.

Consider the simple case where there is only one target application. The Business Process Manager V8.0 integration solution cannot achieve throughput rates higher than the throughput capacity of the target application. This inability to increase throughput applies regardless of the efficiency of the Business Process Manager V8.0 implementation or the size or speed of the system hosting it. Thus, it is critical to understand the throughput capacity of all target applications and service providers and apply this information when designing the end-to-end solution.

Two key aspects of the throughput capacity of a target application or service provider are as follows:

- Response time, both for typical cases and exceptional cases
- Number of requests that the target application can process at the same time (concurrency)

If you can establish performance aspects of the target applications, you can calculate a rough estimate of the maximum throughput capacity. Similarly, if average throughput is known, you can also roughly calculate either one of these two aspects. For example, a target application

that can process 10 requests per second with an average response time of one second, can process approximately 10 requests at the same time:

throughput / response time = concurrency

The throughput capacity of target applications is critical to projecting the end-to-end throughput of an entire application. Also, consider the concurrency of target applications when tuning the concurrency levels of the upstream Business Process Manager V8.0-based components. For example, if a target application can process 10 requests at the same time, tune the process server components that start this application. By tuning these components, the simultaneous request from Business Process Manager V8.0 at least matches the concurrency capabilities of the target.

Additionally, avoid overloading target applications because such configurations do not result in any increase in overall application throughput. For example, if 100 requests are sent to a target application that can process only 10 requests at the same time, throughput does not improve. However, throughput does improve by tuning in a way that the number of requests made matches the concurrency capabilities of the target.

Service providers that might take a long time to reply, either as part of mainline processing or in exception cases, do not use synchronous invocations that require a response. Not using synchronous invocations avoids tying up the business process and its resources until the service provider replies.

# 2.4 Client environments (Process Portal, Process Designer, Business Space)

This section documents best practices for optimizing Business Process Manager Client environments, which include Process Portal, Process Designer, and Business Space solutions.

#### 2.4.1 Optimize the topology

The performance of Asynchronous JavaScript and XML (AJAX) applications, such as those used in Business Process Manager, can be divided into a four-tiered model, as shown in Figure 2-1. Each tier must be optimized to deliver a high-performing solution. Several details for optimizing the topology are described later in this paper, but a context for such a description is presented here.




Figure 2-1 Four tiers of AJAX performance

The four tiers are browser, network, servers, and databases:

#### ▶ Browser

*AJAX applications*, by definition, perform work (to some extent) on the client side, inside the browser. All typical client work, such as building the user interface (UI), is done on the client side, which differentiates these applications from classical web applications, where only the rendering of HTML is done in the browser. Optimizing the browser and client system are key to delivering excellent performance (as described in 2.4.2, "Use a high-performing browser" on page 18 *through* 2.4.5, "Use modern desktop hardware" on page 18).

#### Network

In contrast to static web pages, AJAX applications load the content of a page dynamically as needed, instead of loading the complete page immediately. Instead of one or several requests with significant payloads, AJAX applications often send many requests with smaller payloads. Therefore, delays in the network can have significantly affect response times because they add time to each message. Ultimately, network delays can add up to the most significant factor for the overall page-response time.

Figure 2-1 on page 16 is simplified because the network also plays a role in communications between the servers and the databases and even between servers in a clustered setup. However, because of the nature of AJAX applications, the first point to analyze for delays is generally between the browser and the servers.

#### Servers

The server infrastructure is responsible for handling the requests from the clients that are attached to it, running business applications (processes, state machines, web services, and other applications) and integrating back-end services. The configuration of this infrastructure heavily depends on the chosen topology.

The following servers play an important role for Business Process Manager solutions:

#### HTTP server

An HTTP server is not part of all topologies. However, for environments that aim to serve thousands of users, an HTTP server is indispensable. Both static and dynamic requests from clients come to the HTTP server. This server can cache and then send the static (cached) content back to the client and route dynamic requests to the WebSphere Process Server REST API. Furthermore, an HTTP server can provide load balancing and support high-availability scenarios.

Business Process Manager V8.0 servers (Process Server or Process Center)
 Business Process Manager V8.0 servers execute various business logic (such as BPEL and BPMN business processes), querying task lists, creating and claiming tasks, and other functions. In addition, the Process Center executes authoring requests initiated by the Process Designer.

#### Databases

There are multiple relevant databases depending on the client that is used (Process Designer, Process Portal, or Business Space). Each of these databases must be properly configured and tuned to support the anticipated load.

Use a network with low latency and high bandwidth. Each Business Process Manager client uses multiple HTTP requests per user action, so minimizing the network delay per request is crucial. Network bandwidth is also crucial because some HTTP requests return a significant amount of data. Where possible, use a dedicated network that is both high-speed and high-bandwidth (1 Gb or faster) for connectivity between Business Process Manager clients and servers.

#### 2.4.2 Use a high-performing browser

The choice of browser technology is crucial to Business Process Manager client performance. It is possible that more recent versions of a browser perform better than the older versions of the same browser.

#### 2.4.3 Enable browser caching

Browsers generally cache static data after it is initially retrieved from the server, which can significantly improve response time for scenarios after the cache is primed. This improvement is especially true for networks with relatively high latency. Ensure that the browser cache is active and is effective. Cache settings are browser-specific; see 4.11, "Enable browser caching" on page 78 for further details.

# 2.4.4 Locate servers physically near clients, and databases physically near servers

One factor that influences network latency is the physical distance between servers and clients, and also the distance between the Business Process Manager servers in a cluster and their database (for example, between the Process Server and its databases). When practical, locate Business Process Manager V8.0 servers physically close to each other and to the Business Process Manager clients to minimize the latency for requests.

#### 2.4.5 Use modern desktop hardware

For many Business Process Manager solutions, significant processing is done on the client system (for example, browser rendering). Thus it is imperative to deploy modern desktop hardware with sufficient physical memory and high-speed processors with large caches and fast front-side buses. Monitor your client systems with performance tools (Windows Task Manager or vmstat) to ensure that the client system has sufficient processor and memory resources to ensure high performance.

#### 2.5 Large objects (LOBs)

One issue that is frequently encountered by field personnel is identifying the largest object size that the Business Process Manager V8.0 server, corresponding document management functions, and corresponding WebSphere adapters can effectively and efficiently process. A number of factors affect LOB processing in each of these products. This section presents both a description of the factors involved and practical guidelines for the current releases of these products. The issue of identifying the largest object size primarily applies to 32-bit JVMs because of the constraints on heap sizes in that environment.

The JVM is the single most important factor affecting LOB processing. JVM technology changed starting with Java 5, which was first used by the Business Process Manager products in V6.1.0. Business Process Manager V8.0 uses the Java 6 JVM, which is the follow-on release to Java 5. The suggestions and best practices in this document differ from those in Business Process Manager V6.0.2 and earlier, which used JVM 1.4.2.

In general, objects that are 5 MB or larger might be considered "large" and require special attention. Objects of 100 MB or larger are "very large" and generally require significant tuning to be processed successfully.

#### 2.5.1 Factors affecting LOB size processing

In general, the object size capacity for any installation depends on the size of the Java heap and the load placed on that heap (that is, the live set) by the current level of incoming work. The larger the heap, the larger the business object (BO) that can be successfully processed.

To apply this principle, you must first understand that the object size limit is based on three fundamental implementation facts about JVMs:

#### Java heap size limitations

The limit to the size of the Java heap depends on operating system, but it is not unusual to have a heap size limit of approximately 1.4 GB for 32-bit JVMs. The heap size limit is much higher on 64-bit JVMs and is typically less of a gating factor on modern hardware configurations than the amount of available physical memory. Further details about heap sizes are described in "Increasing the Java heap size to its maximum" on page 63.

#### ► Size of in-memory BOs

BOs, when represented as Java objects, are much larger in size than when represented in wire format. For example, a BO that uses 10 MB on an input Java Message Service (JMS) message queue might result in allocations of up to 90 MB on the Java heap. This condition results from many allocations of large and small Java objects occurring as BO flows through the adapters and Business Process Manager V7.5. A number of factors affect the in-memory expansion of BOs:

- The single-byte binary wire representation is generally converted to multi-byte character representations (for example, Unicode), resulting in an expansion factor of two.
- The BO might contain many small elements and attributes, each requiring a few unique Java objects to represent its name, value, and other properties.
- Every Java object, even the smallest, has a fixed need for resources because of an internal object header that is 12 bytes long on most 32-bit JVMs, and larger on 64-bit JVMs.
- Java objects are padded to align on 8-byte or 16-byte address boundaries.
- As the BO flows through the system, it might be modified or copied, and multiple copies might exist at any time during the end-to-end transaction. Having multiple copies of the BO means that the Java heap must be large enough to host all these BO copies for the transaction to complete successfully.

#### Number of concurrent objects being processed

The size of an object that can be successfully processed decreases as the number of requests being processed simultaneously increases because each request has its own memory usage profile (live set) as it makes its way through the system. Simultaneously processing multiple LOBs dramatically increases the amount of memory required because the total of live sets for the request must fit into the configured heap.

#### 2.5.2 Large object design patterns

The following sections describe the two proven design patterns for processing large objects successfully. In cases where neither design pattern can be applied, consider 64-bit mode. See 2.6, "Considerations for 64-bit mode" on page 21 for details.

Also, for IBM WebSphere ESB and Mediation Flow Components, a developerWorks article is available that details best practices and tuning for large messages:

http://www.ibm.com/developerworks/webservices/library/ws-largemessaging/

#### Batched inputs: Sending large objects as multiple small objects

If a large object must be processed, the solutions engineer must find a way to limit the number of allocated large Java objects. The primary technique for limiting the number of objects involves decomposing large BOs into smaller objects and submitting them individually.

If the large objects are actually collections of small objects, the solution is to group the smaller objects into conglomerate objects less than 1 MB in size. Several customer sites have consolidated small objects in this way, producing good results. If temporal dependencies or an all-or-nothing requirement for the individual objects exists, the solution becomes more complex. Implementations at customer sites demonstrate that dealing with this complexity is worth the effort as demonstrated by both increased performance and stability.

Certain WebSphere adapters (such as the Flat Files adapter) can be configured to use a SplitBySize mode with a SplitCriteria set to the size of each individual object. In this case, a large object is split in chunks (of a size specified by SplitCriteria) to reduce peak memory usage.

#### Claim check pattern: Only a small portion of an input message is used

When the input BO is too large to be carried around in a system and that process or mediation needs only a few attributes, you can use a pattern known as the *claim check pattern*. Using the claim check pattern, as applied to a BO, involves the following steps:

- 1. Detach the data payload from the message.
- 2. Extract the required attributes into a smaller control BO.
- 3. Persist the larger data payload to a data store and store the "claim check" as a reference in the control BO.
- 4. Process the smaller control BO, which has a smaller memory footprint.
- 5. When the solution needs the whole large payload again, check out the large payload from the data store using the key.
- 6. Delete the large payload from the data store.
- 7. Merge the attributes in the control BO with the large payload, taking into account the changed attributes in the control BO.

The claim check pattern requires custom code and snippets in the solution. A less developer-intensive variant is to use custom data bindings to generate the control BO. This approach is limited to certain export and import bindings. The full payload still must be allocated in the JVM.

#### 2.5.3 Data management

The use of document management functions, such as document attachments and the integration capabilities of content that is stored in enterprise content management repositories, might result in large objects. The capacity that is required for processing of documents depends on the size of the Java heap and the load that is placed on that heap (that is, the live set) by the current level of incoming work. The larger the heap, the larger the data that can be successfully processed.

Document attachments and content integration artifacts are stored in the Process Server database. Over time and depending on the size and amount of documents, the database might grow in size. Completed process instances should be archived or deleted (see 4.13.7, "Archiving completed process instances" on page 81 for more information).

#### 2.6 Considerations for 64-bit mode

You can run Business Process Manager applications by using either 32-bit or 64-bit JVMs. However, we suggest 64-bit mode for both Process Server and Process Center because in 32-bit mode, the maximum heap size is limited by the 4 GB address space size. In most 32-bit operating systems, the practical heap size maximum varies in the range of 1.5 GB and 2.5 GB. In contrast, although maximum heap size is essentially limitless in 64-bit mode, standard Java best practices still apply (for example ensure sufficient physical memory exists to back the heap).

The sum of the maximum heap sizes and native memory use of all the Java processes running on a system should not exceed the physical memory available on the system. This total also includes additional memory required for the operating system and other applications. Java processes include threads, stacks, and just-in-time (JIT) compiled code.

Business Process Manager V8.0 servers run most efficiently on a 64-bit JVM instance because of the much larger amount of memory that is accessible in this mode. The performance and memory footprint of a 64-bit runtime server is about the same as the 32-bit version.

Consider the following factors when determining in which of these modes to run:

- ► The 64-bit mode is an excellent choice for applications whose live set approaches or exceeds the 32-bit limits. Such applications either experience OutOfMemory exceptions or suffer excessive time in garbage collection (GC). We consider anything greater than 10% of the time in GC as excessive. These applications exhibit much better performance when allowed to run with the larger heaps they need. However, sufficient physical memory on the system must exist to back the Java heap size.
- ► The 64-bit mode is also an excellent choice for applications that, although well-behaved in 32-bit mode, can be algorithmically modified to perform better with larger heaps. An example might be an application that frequently persists data to a data store to avoid maintaining a very large in-memory cache, even if such a cache greatly improves throughput. Re-coding such an application to trade off the additional space available in 64-bit heaps for less execution time yields better performance.
- ▶ Moving to 64-bit can cause some degradation in throughput if a 32-bit application fits well with a 1.5 GB to 2.5 GB heap and the application is not expected to grow significantly. For these situations where the memory limitation is not a significant factor, using 32-bit JVMs might be a better choice than 64-bit.

#### 2.7 Business Monitor

This section describes best practices for performance with Business Monitor V8.0.

#### 2.7.1 Event processing

A major factor in event processing performance is tuning the Business Monitor database. Ensure adequate buffer pool sizes to minimize disk reading activity and placement of the database logs, which ideally is on a physically separate disk subsystem from the database table spaces.

By default, events are delivered from CEI to the monitor database, bypassing an intermediate queue. We suggest using this default delivery style for better performance because it avoids an additional persistence step in the flow.

For additional background, see "Receiving events using table-based event delivery" in the IBM Business Monitor V8.0 information center:

http://pic.dhe.ibm.com/infocenter/dmndhelp/v8r0m1/index.jsp?topic=/com.ibm.wbpm.mo
n.imuc.doc/inst/cfg qb.html

#### 2.7.2 Dashboard

The platform requirements of Business Space and the Business Monitor widgets on the dashboard are relatively modest compared to the Business Monitor server and the database server. The most important consideration for good dashboard performance is to size and configure the database server correctly. Be sure that it has enough processor capacity for anticipated data mining queries, enough memory for buffer pools, and plenty of disk arms.

#### 2.7.3 Database server

Both event processing and dashboard rely on a fast, well-tuned database server for good performance. The design of the Business Monitor assumes that any customer using it has strong onsite database administrator skills. It is important to apply the database tuning suggestions beginning in 4.13, "General database tuning" on page 80.



# **Development best practices**

This chapter presents best practices that are relevant to solution developers. It addresses modeling, design, and development choices that are made while designing and implementing a Business Process Manager V8.0 solution. Business Process Manager Advanced Edition offers two authoring environments. These authoring environments both interact with the Process Center, which is a shared repository and runtime environment.

- ▶ In the *Process Designer* environment, you can model, develop, and deploy BPMN business processes, which often have human interactions. The Process Designer is the only authoring tool for Business Process Manager V8.0 Standard Edition.
- ▶ In the Integration Designer environment, you can build and implement services that are automated or that start other services, such as web services, enterprise resource applications, or applications running in CICS and IMS. These services and applications exist in the enterprise. It is also the tool to use to author Business Process Execution Language (BPEL) business processes.

Two individuals with separate roles and skill sets work together when developing Business Process Manager applications. These roles correspond to the Process Designer and Integration Designer environments.

- ► The *business author* is responsible for authoring all business processes. The business author is able to use services but is not interested in the implementation details or how they work. The business author uses Process Designer to create business process diagrams (BPDs), and utilizes advanced integration services (AISs) to collaborate with the integration programmer.
- ► The *integration programmer* is responsible for doing all of the integration work necessary to support the processes the business author creates. For example, the integration programmer implements all the AISs and produces mappings between back-end formats and the requirements of current applications. The integration programmer uses Integration Designer.

The remainder of this chapter is organized based on the type of user, with separate sections describing Process Designer (business author) and Integration Designer (integration programmer) best practices. Additionally, the chapter provides developer considerations for browser environments, and for WebSphere InterChange Server migration.

#### 3.1 Process Designer development best practices

The following best practices pertain to the development of high-performance business processes using the Process Designer.

#### 3.1.1 Clear variables in exposed human services that are not intended to end

Data from a taskless human service is not garbage-collected until the service reaches the endpoint. If a human service is developed that is not intended to reach an endpoint, such as a single page or redirect, then memory is not garbage-collected until the Enterprise JavaBeans (EJB) timeout occurs (two hours by default). To reduce memory use for these human services, set variables in the coach to null in a custom HTML block.

#### 3.1.2 Do not use multi-instance loops in the system lane or for batch activities

Where possible, avoid using sub-BPDs as the activity of a multi-instance loop (MIL). This step is not an issue if the first activity is a user task instead of a system lane task. However, do not use MILs for batch or system lane activities. This pattern can generate an excessive number of tokens for the BPD to process. Also, activities in MILs in the system lane are run on a single thread, which is clearly not optimal on multiprocessor core servers.

Figure 3-1 shows an example of a poor BPD design pattern.




Figure 3-1 Poor BPD design pattern




Figure 3-2 shows an example of a good BPD design pattern.

Figure 3-2 Good BPD design pattern

# 3.1.3 Use conditional joins only when necessary

Simple joins use an "and" condition; all lines that head into the join must have an active token for the tokens to continue forward.

By contrast, for conditional joins, all possible tokens must reach the join before they proceed. Thus, if you have a conditional join with three incoming lines, but only two of them currently have tokens (or *might* have tokens by looking upstream), then those two tokens must arrive at the join to proceed. To determine this condition, the BPD engine must evaluate all possible upstream paths to determine whether the tokens can arrive at the join. This evaluation can be expensive for large, complex BPDs. Use this capability judiciously.

# 3.1.4 Guidelines for error handling

Avoid global error handling in a service, which can use an excessive amount of server processor utilization and can even result in infinite loops in coaches.

When catching errors on an activity in a BPD, do not route the error back to the same activity. Doing so causes the server to thrash between the BPD and service engine, using a large amount of Process Server processor time and also database processing.

# 3.1.5 Use sequential system lane activities efficiently

Each system lane activity is considered a new Event Manager task, which adds a task transition in the Process Server. These task transitions are expensive. If your BPD contains multiple system lane service tasks in a row, use one system lane task that wraps the others to minimize the extra resources needed for these transitions. Using one system lane task also applies for multiple consecutive tasks in a participant lane, although that pattern is much less common because generally an action is necessary between each task in a participant lane.

Figure 3-3 demonstrates a poor usage pattern (with multiple consecutive system lane activities).




Figure 3-3 Poor BPD usage pattern

Figure 3-4 shows a more optimal usage pattern (one system lane activity that incorporates the multiple activities in Figure 3-3).




Figure 3-4 Good BPD usage pattern

# 3.1.6 Ensuring the Process Center is tuned

Because all Process Designer users access the Process Center, and for many cases use a significant amount of resources on the Process Center (and its database), optimizing its configuration is essential. See 4.6, "Process Center tuning" on page 62 for more information about this topic.

# 3.1.7 Using a fast connection between Process Designer and Process Center

The Process Designer interacts frequently with the Process Center for authoring tasks. Take steps to expedite interaction between these components. See "Use a fast connection between Process Designer and Process Center" on page 9 to learn more about optimizing the connection between Process Designer and the Process Center.

# 3.1.8 Preventing WSDL validation from causing slow web service integrations

The Process Designer web service integration connector goes through several steps at run time to start a web service. First, the system generates the SOAP request from the metadata and the business objects (BOs). Then, the system validates the request against the Web Services Description Language (WSDL), makes the actual SOAP call over HTTP, and parses the results back into the BOs. Each of these steps potentially has some latency. Therefore, an important step is to make sure that the actual web service response time is fast and that the request can be quickly validated against the WSDL. Speed is especially important for web services that might be started frequently.

The two major causes of delays in validation are as follows:

- Slow responses in retrieving the WSDL
- ► Deeply nested WSDL include structures

If the source of the WSDL is a remote location, the latency of retrieving that WSDL over HTTP adds to the overall latency. Thus, a slow connection, a slow proxy, or a slow server can all potentially increase the latency of the complete web service call. If that WSDL also nests additional WSDL or XML Schema Definition (XSD) files through imports or includes, then after the main WSDL is retrieved, the subfiles must also be retrieved. The validation continues to recurse through all WSDLs or XSDs that are nested within the subfiles. Therefore, in a case where there are multiple levels of nesting, many HTTP calls must make many calls to retrieve the complete WSDL document, and the overall latency can become high.

To alleviate this type of latency, you can store a local copy of the WSDL either in the local file system or somewhere where HTTP response is fast. For even better performance, this local copy can be "flattened," removing the nesting by manually replacing all of the include statements with the actual content.

# 3.2 Integration Designer best practices

The following best practices pertain to the development of well-performing solutions through the Integration Designer.

# 3.2.1 Using share-by-reference libraries where possible

Often, definitions of interfaces, BOs, data maps, mediation subflows, relationships, roles, and web service ports must be shared so that resources in several modules can use them. These resources are stored in the library. Libraries can be deployed in several ways:

- With a process application
- ► With the dependent module
- Globally

You can make your choice in the dependency editor. If you associate a library with a process application, then you select the application in the editor. The library is shared within the deployed process application, meaning only one copy is in memory. We call this type of library a *share-by-reference library*. The share-by-reference library is a feature that was introduced in Business Process Manager V7.5.

If you choose to deploy a library with the module, the deployment action creates a copy of the library for each module when the module is deployed. This type of library is known as a *share-by-value* library. Deploying the library with the module is the default setting when the library is not associated with a process application.

More details about Business Process Manager V8.0 library types is in "Libraries" in the information center for IBM Business Process Manager, Version 8.0, all platforms:

http://pic.dhe.ibm.com/infocenter/dmndhelp/v8r0mx/index.jsp?topic=%2Fcom.ibm.wbpm.wid.main.doc%2Fnewapp%2Ftopics%2Fclibrary.html

# 3.2.2 Ensure content in Toolkits is needed for multiple applications

Toolkits are copied into each process application that uses them. As such, ensure that a Toolkit's content is only artifacts that are needed by multiple process applications to reduce the size and complexity of the PC Repository. Include process application-specific content only in the process application itself.

# 3.2.3 Advanced Content Deployment considerations

Content included in a Process Application (PA) or Toolkit that is authored with the Integration Designer is considered Advanced Content. When the tip or snapshot of a PA or Toolkit is activated or deployed, Advanced Content is processed over a different path than Standard Content. Deployment of Advanced Content often takes much longer to deploy than Standard Content. This is because Advanced Content is packaged into SCA modules and libraries, and deployed as Business Level Applications (BLAs) and J2EE EARs on the Process Center or Process Server. Because each deployed BLA and EAR consumes a non-trivial amount of resource on the server (memory, disk space, CPU cycles), Advanced Content deployments should be done the minimum number of times that is practical. Also, Snapshots and PA or Toolkit Tips that are no longer needed should be proactively cleaned up by deactivating and undeploying their Advanced Content. These topics are discussed further in the remainder of this section.

To check how many BLAs are installed on the server, use the administrative console on the Deployment Manager and go to **Applications**  $\rightarrow$  **Application Types**  $\rightarrow$  **Business-level applications.** 

You will see the list of all installed BLAs, which includes customer PAs and Toolkits, and also Business Process Manager product applications. If there are more than approximately 50 customer BLAs installed, consider how the number can be reduced. Snapshots can be deactivated and undeployed through the Process Center web page by going to the Snapshots page of the corresponding PA or Toolkit, as follows:

- 1. Access the Snapshots page
- 2. Click the name of the PA or Toolkit on the Process Apps or Toolkits tab of the Process Center web page.
- 3. Click the down arrow next to the Snapshot name.
- 4. If the Snapshot is Active and Deployed, click **Deactivate**.
- Click Undeploy.
- Confirm that the corresponding BLA was uninstalled through the deployment manager administrative console.

If you cannot remove a BLA through the Process Center web page, you can use the Deployment Manager administrative console to perform this action. Stop and uninstall the corresponding J2EE EARs, and delete the corresponding BLAs.

During iterative development of a solution, the amount of Advanced Content to manage can be minimized by integrating Advanced Content as late in the development cycle as is practical. The reason is because activating a snapshot, or deploying a tip, can take much longer when Advanced Content is involved. Thus, testing small incremental changes often becomes more time-consuming when a large amount of Advanced Content is involved. Also, Advanced Content should typically be relatively static after it is deployed, because the implementation should meet the terms of a service level agreement (SLA) that was already agreed to as part of the solution development cycle. This recommendation should be balanced with testing needs and the overall schedule of the solution development cycle.

When designing the PA and Toolkit dependency graph, consider the server overhead that is attributable to Advanced Content. Include Advanced Content in Toolkits only if *every* PA that references the Toolkit needs all of the contained Advanced Content. Toolkits are copied "by value" into dependent process applications and Toolkits, so any Advanced Content will be duplicated on the server in every PA or Toolkit that references it. Including Advanced Content in Toolkits should be minimized because of the additional cost of Advanced Content.

Because deployment of Advanced Content uses BLAs and J2EE EARs, deployment can be disk-intensive. Deployment of Advanced Content occurs in multiple phases, with some processing and disk activity taking place on the deployment manager (dmgr) node, and some on each AppTarget cluster member. The installation directory of the profiles for the dmgr and cluster members should be stored on fast disk subsystems, such as server-class hardware with RAID adapters with a write-back cache and multiple physical backing disks.

Deployment of Advanced Content can also be CPU-intensive. For process servers, install snapshots with Advanced Content during periods of low activity so that users are not affected. For Process Center servers, ensure that the dmgr and cluster members are installed on servers with multiple CPU cores. This way enables the Process Center to remain responsive during periods of Advanced Content deployment. For clustered Process Centers, use a dynamic load balancer that can detect CPU consumption on the cluster members to avoid sending work to cluster members that might be processing a long-running Advanced Content deploy operation.

# 3.2.4 Business object parsing mode considerations

This section describes how and why to choose the BO parsing mode. Two options for this mode exist: *eager* parsing mode and *lazy* parsing mode.

#### Overview

WebSphere Business Process Manager V7.0.0.1 introduced BO lazy parsing mode. In this mode, when BOs are created, their properties are not populated until they are accessed by the application. Also, when reading XML input, the stream is incrementally parsed and its properties do not materialize until they are accessed.

In contrast, with eager parsing mode, the input XML stream is immediately and fully parsed (with some exceptions for specific mediation primitives) and materializes into a complete in-memory data object representation.

Lazy parsing uses the XML Cursor Interface (XCI) implementation of Service Data Objects (SDOs), provided by the WebSphere Application Server Feature Pack for Service Component Architecture (SCA), which is delivered as part of Business Process Manager V8.0. In this mode, the input XML stream remains in memory throughout the lifetime of the corresponding BO. The cursor-based XML parser creates nodes in memory only when the nodes are traversed. Properties and attributes are evaluated only when the application requests them. Parsing the XML stream in this fashion delivers better performance than complete parsing for many applications in eager mode. This improvement is especially evident if only a small portion of the BO is accessed during the application execution.

Lazy parsing also reuses the XML stream when BOs are serialized, for example, for outbound service calls. The result is faster serialization because serializing the entire in-memory BO into XML strings is not necessary. Lazy parsing automatically detects namespaces in the output stream that differ from the namespaces in the original input stream, and corrects them. This form of serialization is used for all bindings and internal Business Process Manager runtime components, such as the Business Process Choreographer (BPC) container, and when custom code calls BO serialization.

To further optimize performance, lazy parsing also employs a technology referred to as *copy-on-write*, where properties in BOs are lazily copied. When the copy operation initially takes place, the target BO points only to the node tree of the source BO. Lazy parsing copies no properties. Subsequent modifications of either the source or target BO trigger a split of the affected node in the BO tree, copying BO properties only as needed. Modifications occur in the local copy of the corresponding node. Copy-on-write is transparent to the application.

#### Setting parsing mode

In Business Process Manager V8.0, the default parsing mode is the lazy mode for newly developed applications in Integration Designer V8.0. Applications moved from WebSphere Process Server V7.0.0.3 and earlier releases continue to run in the eager parsing mode. However, for these older applications, you can manually enable lazy parsing mode through Integration Designer, which provides a property for each module and library to configure the XML parsing mode to either eager or lazy.

Figure 3-5 on page 31 shows the Integration Designer panel that the system displays during creation of a library. At this point, you can specify whether it can be included in an eager parsing or lazy parsing module, or both. The default is set to lazy parsing when the library is initially created. When both parsing modes are selected for the library, the module in which the library is located determines the actual parsing mode at run time.




Figure 3-5 Lazy parsing for new library

When creating a module, you must choose eager or lazy parsing mode. The default mode is lazy parsing. Figure 3-6 shows the Integration Designer panel for creating modules.




Figure 3-6 Lazy parsing for new module

In Business Process Manager V8.0, lazy parsing delivers excellent performance for XML-based applications that use BOs or messages approximately 3 KB or larger. The performance of lazy parsing is generally better than or about equal to eager parsing for other scenarios.

# Applications benefiting from lazy parsing

This section provides general guidance for choosing the correct parsing mode, and best practices to follow when choosing one mode over the other. However, we suggest that you benchmark your application in both parsing modes to determine which mode best suits the specific characteristics of your application.

The primary performance benefits that are derived from lazy parsing are delayed parsing and parsing only the properties accessed by the application. Applications exhibiting any of the following characteristics are candidates for taking advantage of lazy parsing for better performance. As demonstrated in the measurements, the performance improvement when using lazy parsing can be significant.

- Only applications that use XML data streams can benefit from lazy parsing. For example, applications that use web services bindings, synchronous or asynchronous SCA bindings, or the Java Message Service (JMS) binding with the XML data handler can potentially benefit from lazy parsing mode.
- ▶ Applications with medium to large XML data streams are likely to see performance improvements when lazy parsing is used. The performance benefit increases as the size of the XML data stream increases. In the workloads we studied, lazy parsing performed better than eager mode when the BOs were approximately 3 KB or larger. The BO size differs depending on the composition of your application, so use these findings as a general guideline.
- ▶ Applications that access a small portion of an XML data stream are likely to see greater performance benefits from lazy parsing. Access to a BO is defined as reading the value of a property, updating a property value, or adding a property to a BO. Lazy parsing allows the unmodified portion of the data stream to pass through the system with minimal required resource usage. As opposed to eager parsing, the less an application accesses its BOs, the higher performance improvement it achieves by enabling lazy parsing.
- Mediation Flow Components (MFC) with multiple mediation primitives are likely to see performance improvements when you use lazy parsing. When using eager parsing, BOs are often serialized before starting the next mediation primitive and then deserialized after that mediation primitive is started. Lazy parsing mode reduces the cost of each serialization and deserialization by preventing unmodified properties from unnecessarily materializing in the data stream.

Applications that fall within these parameters likely benefit from lazy parsing. Applications that do not have those attributes produce little difference in performance and can run in either lazy or eager parsing modes. For example, applications that parse non-XML data streams, such as WebSphere adapters and non-XML data handlers, might perform similarly, whether you choose lazy or eager parsing mode in Business Process Manager V8.0. This similarity is also true of applications that create BOs directly using the BOFactory service and applications that use small XML messages (as a general guideline, greater than 3 KB).

MFCs that access only the message header or contain a single mediation primitive, might see slightly better performance when using eager parsing. For example, a ServiceGateway with a single filter mediation routing based on the header content might perform better. However, adding multiple mediation primitives to a flow performance is likely to perform better in lazy parsing mode.

## Minimizing use of mixed parsing modes between modules

Sometimes it is necessary to direct some modules to use eager parsing while others use lazy parsing. For better performance, however, avoid using this mixed mode for application modules that frequently interact with each other. For example, if module A starts module B

through the synchronous SCA binding on each transaction, it is better to set modules A and B to both use either eager parsing or lazy parsing.

The interaction between modules with different parsing modes takes place through serialization and deserialization, which can negatively affect performance. If using a mixed mode is unavoidable, starting an application from an eager parsing module to a lazy parsing module is more efficient than the other way around. The output from the eager parsing module is serialized into an XML string, and the target module using lazy parsing still benefits fully from delayed parsing, producing this efficiency.

# **Share-by-reference libraries**

Lazy parsing is optimized to use share-by-reference libraries. When a BO travels from one module to another as a parameter of a synchronous SCA service invocation, a lazy copy is used if the source and target modules share the BO schema through a share-by-reference library. Without the share-by-reference optimization, the caller serializes the BO and the callee deserializes the BO.

# Differences in behavior for lazy parsing and eager parsing

If you are changing an application that was originally developed with eager parsing to use lazy parsing, be aware of the differences in behavior between each mode, as summarized here. Also consider the behavior differences between each node if you are planning to switch an application between lazy and eager parsing mode.

## Error handling

If the XML byte stream being parsed is ill-formed, parsing exceptions occur:

- With eager parsing, the exceptions occur as soon as the BO is parsed from the inbound XML stream.
- ► With lazy parsing, the parsing exceptions occur latently when the application accesses the BO properties and parses the portion of the XML that is ill-formed.

To properly handle ill-formed XML for either parsing mode, select one of the following options:

- Deploy a Mediation Flow Component on the application edges to validate inbound XML.
- Author lazy error-detection logic at the point where BO properties are accessed.

## Exception stacks and messages

Because eager and lazy parsing have different underlying implementations, stack traces that are generated by the BO programming interfaces and services have the same exception class name. However, stack traces might not contain the same exception message or wrapped set of implementation-specific exception classes.

#### XML serialization format

Lazy parsing provides a fast serialization optimization that attempts to copy unmodified XML from the inbound data stream to the outbound data stream upon serialization. The fast serialization improves performance, but the resultant serialization format of the outbound XML data stream might be syntactically different than if the entire BO is updated in lazy parsing, or if eager parsing is used.

The output XML serialization format might not be precisely syntactically equivalent across these cases. However, the semantics of the XML data streams are equivalent, regardless of the parsing mode, and the resultant XML can be safely passed between applications running in different parsing modes with semantic equivalence.

## Business object instance validator

The lazy parsing instance validator provides a higher fidelity validation of BOs, particularly for facet validation of property values. Because of these improvements in fidelity, the lazy parsing instance validator catches functional issues not detected in eager parsing mode and provides more detailed error messages.

## Migration of XSL style sheets

When an application authored using WebSphere Integration Developer V7.0.0.1 or earlier, the application is migrated using Integration Designer V8.0 and rebuilt. Extensible Stylesheet Language Transformation (XSLT) style sheets are regenerated from the associated map files. Extensible Style Sheet Language (XSL) style sheets built by Integration Designer V8.0 no longer contain white space or indent directives. This change improves performance in lazy parsing mode. However, if an XSLT primitive refers directly to manually edited style sheet, the style sheet is not regenerated when the application is built. In this case, performance improves by removing the white space directive (<xs1:strip-space elements="\*"/>) if it appears, and by ensuring that indentation is disabled (indent="no") unless required.

#### Private APIs

The BO programming model provides support for BO application programming interfaces (APIs) and a set of Service Data Object (SDO) APIs. In some cases, applications might use additional implementation-specific APIs that are not part of the supported APIs for BOs. For example, an application might use the Eclipse Modeling Framework (EMF) APIs. Although these APIs might have worked in prior Business Process Manager releases and in eager parsing mode, they are not supported APIs for accessing BOs. EMF APIs are considered private to the implementation of BOs and should not be used by applications.

For these reasons, remove private APIs from the application and ensure that all BO access takes place using the supported API set.

#### Service Message Object Eclipse Modeling Framework APIs

A Mediation Flow Component makes it possible to manipulate message content using the Java classes and interfaces provided in the com.ibm.websphere.sibx.smobo package. For lazy parsing, the Java interfaces in the com.ibm.websphere.sibx.smobo package can still be used. However, methods that refer directly to Eclipse Modeling Framework (EMF) classes and interfaces or that are inherited from EMF interfaces are likely to fail. Also, the Service Message Object (SMO) and its contents cannot be cast to EMF objects when using lazy parsing.

#### Migration

All applications developed before Business Process Manager V7.5 used eager parsing mode, by default. When Business Process Manager runtime migration moves these applications, they continue to run in eager parsing mode.

To enable an application, that was originally developed using eager parsing, to use lazy parsing, first use the Integration Designer to move the artifacts of the application. After migration, use the Integration Designer to configure the application to use lazy parsing.

For information about moving artifacts in the Integration Designer, see "Migrating source artifacts" in the IBM Business Process Manager Information Center:

http://pic.dhe.ibm.com/infocenter/dmndhelp/v8r0mx/index.jsp?topic=%2Fcom.ibm.wbpm.wid.imuc.doc%2Ftopics%2Ftmigsrcartwid.html

For information about setting the parsing mode, see "Configuring the business object parsing mode of modules and libraries" in the IBM Business Process Manager Information Center:

http://pic.dhe.ibm.com/infocenter/dmndhelp/v8r0mx/index.jsp?topic=%2Fcom.ibm.wbpm.wid.main.doc%2Fnewapp%2Ftopics%2Ftconfigbo.html

# 3.2.5 Service Component Architecture considerations

This section describes the SCA authoring considerations for Business Process Manager performance.

# Cache results of ServiceManager.locateService()

When writing Java code to locate an SCA service, either within a Java component or a Java snippet, consider caching the result for future use, as service location is a relatively expensive operation. Code that is generated in Integration Designer does not cache the locateService result, so editing is required.

# Reducing the number of Service Component Architecture modules when appropriate

When Business Process Manager V8.0 components are assembled into modules for deployment, many factors are involved. Performance is a key factor, but you must consider maintainability, version requirements, and module ownership also. In addition, more modules can allow for better distribution across servers and nodes. It is important to recognize that modularization also has a cost. When components are placed together in a single server instance, package them within a single module for best performance.

# Using synchronous Service Component Architecture bindings across local modules

For cross-module invocations, where the modules are likely to be deployed locally (that is, within the same server JVM), use the synchronous SCA binding because this binding is optimized for module locality and performs better than other bindings. Synchronous SCA is as expensive as other bindings when invocations are made between modules in separate Business Process Manager server instances.

# Using multi-threaded Service Component Architecture clients to achieve concurrency

Synchronous components that are started locally (that is, from a caller in the same server JVM) run in the context of the thread of the caller. Thus the caller must provide concurrency, if desired, in the form of multiple threads.

#### Adding quality of service qualifiers at appropriate level

You can add quality of service (QoS) qualifiers, such as Business Object Instance Validation, at the interface level or at an operation level within an interface. Because additional processor usage is associated with QoS qualifiers, do not apply a qualifier at the interface level if it is not needed for all operations of the interface.

# 3.2.6 Business Process Execution Language business process considerations

This section presents considerations for authoring performance specific to BPEL business processes.

## Modeling best practices for activities in a business process

For best performance, use the following guidelines when modeling a BPEL business process:

- ▶ Use the Audit Logging property for Business Processes only setting if you need to log events in the Business Process Choreographer database (BPEDB). You can set this property at the activity or process level. If you set it at the process level, the setting is inherited by all activities.
- ► For long-running processes, in Integration Designer, click **Properties** → **Server**, and clear the **Enable persistence and queries of business-relevant data** property for both the process and for each individual BPEL activity. Enabling this flag causes details of the execution of this activity to be stored in the BPC database, which increases the load on the database and the amount of data stored for each process instance. Use this setting only if you must retrieve specific information later.
- ► For long-running processes, a setting of **Participates** on all activities generally provides the best throughput performance. See "Avoiding two-way synchronous invocation of an asynchronous target" on page 39 for more details.
- ► Human tasks can be specified in business processes (for example, process administrators), start activities, and receive activities. Specify human tasks only if necessary. When multiple users are involved, use group work items (people assignment criterion: Group) instead of individual work items for group members (people assignment criterion: Group Members).

#### Avoiding two-way synchronous invocation of long-running processes

When designing long-running business process components, ensure that callers of a two-way (request/response) interface do not use synchronous semantics because this function ties up the caller's resources (such as threads and transactions) until the process completes. Instead, start such processes either asynchronously, or through a one-way synchronous call, where no response is expected. In addition, calling a two-way interface of a long-running business process synchronously introduces difficulties when exceptions occur. Suppose that a non-interruptible process calls a long-running process using the two-way request/response semantics, and the server fails after the long-running process completes, but before the caller's transaction is committed. The following results occur:

- ▶ If the caller was started by a persistent message, upon server restart, the caller's transaction is rolled back and tried again. However, the result of the execution of the long-running process on the server is not rolled back because it was committed before the server failure. As a result, the long-running process on the server runs twice. This duplication causes functional problems in the application unless corrected manually.
- ▶ If the caller was not started by a persistent message, and the response of the long-running process was not submitted yet, the process ends in the failed event queue.

# Minimizing the number and size of Business Process Execution Language variables and business objects

Use the following guidelines when you define BPEL variables and BOs:

- Use as few variables as possible and minimize the size and the number of BOs used. In long-running processes, each commit saves modified variables to the database (to save context), and multiple variables or large BOs make this process costly. Smaller BOs are also more efficient to process when emitting monitor events.
- ► Specify variables as data type variables. This specification improves runtime performance.
- ▶ Use transformations (maps or assigns) to produce smaller BOs by mapping only fields that are necessary for the business logic.

#### 3.2.7 Human task considerations

Follow these guidelines when developing human tasks for BPEL business processes:

- ▶ Use group work items for large groups (people assignment criterion: Group) instead of individual work items for group members (people assignment criterion: Group Members).
- ▶ Use native properties on the task object rather than custom properties where possible. For example, use the priority field instead of creating a custom property priority.
- ► Set the transactional behavior to commit after if the task is not part of a page flow. This setting improves the response time of task complete API calls.

# 3.2.8 Business process and human tasks client considerations

Consider the following information when developing effective BPEL business process and human task clients:

- ► Do not frequently call APIs that provide task details and process details, such as htm.getTask(). Use these methods only when required to show the task details of a single task, for example.
- Do not put too much work into a single client transaction.
  - In servlet applications, a global transaction is typically not available. If the servlet calls the Human Task Manager (HTM) and Business Flow Manager (BFM) APIs directly, transaction size is typically not a concern.
  - In Enterprise JavaBeans (EJB) applications, make sure that transactions are not too time-consuming. Long-running transactions create long-lasting locks in the database, which prevent other applications and clients to continue processing.
- Choose the protocol that best suits your needs.
  - In a J2EE environment, use the HTM and BFM EJB APIs. If the client application is running on a Business Process Manager server, use the local EJB interface.
  - In a Web 2.0 application, use the REST API.
  - In an application that runs remote to the process container, the web services API is an option.

Client systems that follow a page-flow pattern should consider the following issues:

- Use the completeAndClaimSuccessor() API if possible. This API use provides optimal response time.
- ► Applications that assign the next available task to the user can use the following method on the Human Task Manager EJB interface. This method implements a performance-optimized mechanism to handle claim collisions.
  - claim(String queryTableName, ...)
- ▶ Do not put asynchronous invocations between two steps of a page flow because the response time of asynchronous services increases as the load on the system increases.
- Where possible, do not start long-running subprocesses between two steps of a page flow because long-running subprocesses are started using asynchronous messaging.

Clients that present task lists and process lists should consider the following factors:

- ► Use query tables for task list and process list queries.
- ▶ Do not loop over the tasks shown in the task or process list and run an additional remote call for each object. This practice prevents the application from providing good response times and good scalability.
- ▶ Design the application so that all information is retrieved from a single query table during task list and process list retrieval. For example, do not make calls to retrieve the input message for task list or process list creation.

## 3.2.9 Transactional considerations

One of the strengths of the Business Process Manager BPEL platform is the precise control it provides for specifying transactional behavior. When modeling a process or mediation assembly, be sure the modeler carefully designs the transaction boundaries as dictated by the needs of the application because boundaries are expensive in terms of system resources. The objective of this section is to guide the modeler to avoid unnecessary transaction boundaries. The following list details several guiding principles:

- ► The throughput of a particular usage scenario is inversely related to the number of transaction boundaries traversed in the scenario, so fewer transactions is faster.
- ► In user-driven scenarios, improving response time might require more granular transaction boundaries, even at the cost of throughput.
- ► Transactions can span across synchronous invocations but cannot span asynchronous invocations.
- Avoid synchronous invocation of a two-way asynchronous target. The failure recovery of a caller transaction can be problematic.

# Taking advantage of Service Component Architecture transaction qualifiers

In an SCA assembly, you can reduce the number of transaction boundaries by allowing transactions to propagate across components. For any pair of components where you want to reduce the number of transaction boundaries, use the following settings:

- ► For the reference of the calling component: SuspendTransaction= false
- ► For the interface of the called component: joinTransaction= true
- ► For implementation of both components: Transaction= any global

These settings assume that the first component in such a chain either starts or participates in a global transaction.

# Avoiding two-way synchronous invocation of an asynchronous target

If the target component must be started asynchronously and its interface is of two-way request/response style, then the target cannot be safely started through synchronous SCA calls. After the caller sends the request to the target, it waits for response from the target. Upon receiving the request, the asynchronous target starts a new transaction. Upon processing the request, the target returns the response asynchronously to the caller through the response queue. If a system failure occurs after the caller successfully sends the request but before receiving the response, the caller transaction is rolled back and tried again. As a result, the target is started a second time.

# Taking advantage of transactional attributes for activities in long-running processes

Although SCA qualifiers control component-level transactional behavior, additional transactional considerations in long-running business processes can cause activities to run in multiple transactions. You can change the scope of those transactions and the number of transactions using the transactional behavior settings on Java Snippet, Human Task, and start activities. For a detailed description of these settings, see "Transactional behavior of business processes" in the Business Process Manager 8.0 information center:

http://pic.dhe.ibm.com/infocenter/dmndhelp/v8r0mx/index.jsp?topic=%2Fcom.ibm.wbpm.bpc.doc%2Ftopics%2Fcprocess\_transaction\_macro.html

You have four setting choices for transactional behavior:

#### Commit before

Use the Commit before setting in parallel activities that start new branches to ensure parallelism. As noted in the information center, you must consider other constraints.

#### ▶ Commit after

Use Commit after for inline human tasks to increase responsiveness to human users. When a human user issues a task completion, the thread/transaction handling that action, is used to resume navigation of the human task activity in the process flow. The user's task completion action does not complete until the process engine commits the transaction.

Starting with WebSphere Process Server 6.2.0, Receive and Pick activities in BPEL flow are allowed to define their own transactional behavior property values. If not set, the default value of initiating a Receive or Pick activity is Commit after. Consider using Participates where possible because that behavior performs better.

#### Participates

If the Participates setting is used, the commit is delayed and forces a longer response time for the user. Only the Participates setting does not require a new transaction boundary. The other three settings require the process flow container to start a new transaction before executing the activity, after executing the activity, or both.

In general, the Participates attribute provides the best throughput and should be used where possible. This suggestion is true for both synchronous and asynchronous activities. In the two-way asynchronous case, it is important to understand that the calling transaction always commits after sending the request. The Participates setting refers to the transaction started by the process engine for the response. When set, this setting allows the next activity to continue on the same transaction.

In special cases, transaction settings other than Participates might be preferable. Review the Business Process Manager 8.0 information center for more guidance about this issue.

#### Requires own

The Requires own setting requires that a new transaction be started.

# 3.2.10 Invocation style considerations

This section explains invocation style considerations.

# Using asynchronicity judiciously

Components and modules might be wired to each other either synchronously or asynchronously. The choice of interaction style can have a profound impact on performance. Exercise care when making this choice.

# Setting the Preferred Interaction Style to Synchronous when possible

Many Business Process Manager server component types (such as interface maps or business rules) start their target components based on the Preferred Interaction Style setting of the target interface. Because synchronous cross-component invocations perform better, set the Preferred Interaction Style to Synchronous when possible. Change this setting to Asynchronous only in specific cases. Such cases might include starting a long-running business process, or more generally, where the target component requires asynchronous invocation.

Starting with WebSphere Integration Developer V6.2 (now Integration Designer), when a new component is added to an assembly diagram, its Preferred Interaction Style is set to Synchronous, Asynchronous, or Any, based on the component. In previous releases of the Integration Designer (then called WebSphere Integration Developer), the default initial setting of Preferred Interaction Style was set to Any unless explicitly changed by the user. If the Preferred Interaction Style of a component is set to Any, how the component is started is determined by the caller's context. If the caller is a long-running business process, a Preferred Interaction Style setting of Any is treated as asynchronous. If the caller is a non-interruptible business flow, a Preferred Interaction Style setting of Any is treated as synchronous.

See "Taking advantage of transactional attributes for activities in long-running processes" on page 39 for more information about the invocation logic of processes

The following list details additional considerations for invocation styles:

- ▶ When the Preferred Interaction Style of an interface is set to Asynchronous, it is important to realize the downstream implications. Any components started downstream inherit the asynchronous interaction style unless they explicitly set the Preferred Interaction Style to Synchronous.
- ► At the input boundary to a module, exports that represent asynchronous transports such as IBM WebSphere MQ, JMS, or Java EE Connector Architecture (with asynchronous delivery set), set the interaction style to Asynchronous. This setting can cause downstream invocations to be asynchronous if the Preferred Interaction Style is Any.
- ► For an SCA import, you can use Preferred Interaction Style to specify whether the cross-module call should be Synchronous or Asynchronous.
- ► For other imports that represent asynchronous transports such as WebSphere MQ or JMS, it is not necessary to set the Preferred Interaction Style to Asynchronous. Doing so introduces an unnecessary asynchronous hop between the calling module and the invocation of the transport.

# Minimizing cross-component asynchronous invocations within a module

Asynchronous invocations are intended to provide a rich set of qualities of service, including transactions, persistence, and recoverability. Therefore, think of an asynchronous invocation as a full messaging hop to its target. When the intended target of the invocation is in the same module, a synchronous invocation yields better performance.

Some qualities of services (such as event sequencing and store-and-forward) can only be associated with asynchronous SCA calls. Consider the performance impact of asynchronous invocations when setting these qualities of service.

# Performance considerations for asynchronous invocation of synchronous services in a FanOut/FanIn block

Do not select asynchronous (deferred response interaction) service invocations for services with synchronous bindings (for example, web services) unless there is an overriding need and the non-performance implications for this style of invocation are understood.

Apart from the performance implications of calling a synchronous service asynchronously, you must consider reliability and transactional aspects. Generally, use asynchronous callouts only for idempotent query type services. If you need to guarantee that the service is called only once, do not use asynchronous invocation. Provide complete guidance on the functional applicability of using asynchronous callouts in your mediation flow is beyond the scope of this paper.

More information is in the Integration Designer help documentation and Business Process Manager V8.0 Information Center:

http://pic.dhe.ibm.com/infocenter/dmndhelp/v8r0mx/index.jsp?topic=%2Fcom.ibm.wbpm.main.doc%2Fic-homepage-bpm.html

Assuming that asynchronous callouts are functionally applicable for your configuration, there might be a performance reason for starting a service in this style. However, understand that asynchronous processing is inherently more expensive in terms of processor cycles because of the additional messaging resources incurred by calling a service this way.

Additional operational considerations in choosing synchronous or asynchronous mode might apply. For example, asynchronous invocations use the service integration bus messaging infrastructure, which in turn uses a database for persistence. Synchronous invocations perform well with basic tuning of the JVM heap size and thread pools, but for asynchronous invocations, SCA artifacts require review and tuning. This requirement includes tuning the SCA messaging engine (see 4.3.7, "Messaging engine properties" on page 56), data sources (see 4.3.6, "Java Database Connectivity data source parameters" on page 55), and the database itself. For the data source, the tuning for JMS bindings in this paper can provide guidance as the considerations are the same.

If multiple synchronous services with large latencies are called, asynchronous invocations can reduce the overall response time of the mediation flow, but at the expense of increasing the internal response time of each individual service call. This reduction of overall response time and increase of internal response time assume that asynchronous callouts are configured with parallel waiting in the FanOut section of the flow under the following conditions:

- ► With iteration of an array when configuring the FanOut to check for asynchronous responses after all or N messages are fired
- With extra wires or FlowOrder primitive (by default)

If a number of services in a FanOut section of a mediation flow exists, calling these services synchronously results in an overall response time equal to the sum of the individual service response times.

Calling the services asynchronously (with parallel waiting configured) results in a response time of at least the largest individual service response time in the MFC. The response time also includes the sum of the time taken by the MFC to process the remaining service callout responses on the messaging engine queue.

For a FanOut/FanIn block, the processing time for any primitives before or after the service invocations must be added in both cases.

To optimize the overall response time when calling services asynchronously in a FanOut/FanIn section of a mediation flow, start the services in the order of expected latency (highest latency first), if known.

You must consider the trade-off between parallelism and additional asynchronous processing. The suitability of asynchronous processing depends on the size of the messages being processed, the latency of the target services, the number of services being started, and any response time requirements expressed in service level agreements (SLAs). We suggest running performance evaluations on mediation flows, including FanOuts with high latency services, if you are considering asynchronous invocations.

The default quality of service-on-service references is Assured Persistent. You can gain a substantial reduction in asynchronous processing time by changing this setting to Best Effort (non-persistent). This change eliminates I/O to the persistence store, but the application must tolerate the possibility of lost request or response messages. This level of reliability for the service integration bus can discard messages under load and might require tuning.

# 3.2.11 Large object considerations

This section presents best practices for performance (particularly memory use) when using large objects (LOBs). Very large objects put significant pressure on Java heap use, particularly for 32-bit JVMs. The 64-bit JVMs are less susceptible to this issue because of the large heap sizes that you can be configure, although throughput, response time, and overall system performance can still be impacted by excessive memory usage. Follow these practices to reduce the memory pressure and avoid OutOfMemory exceptions and improve overall system performance.

# Avoiding lazy cleanup of resources

Lazy cleanup of resources adds to the live set required when processing large objects. If you can clean up any resources (for example, by dropping object references when no longer required), do so as soon as is practical.

#### Avoiding tracing when processing large business objects

Tracing and logging can add significant memory resources. A typical tracing activity is to dump the BO payload. Creating a string representation of a large BO can trigger allocation of many large and small Java objects in the Java heap. For this reason, avoid turning on tracing when processing large BO payloads in production environments.

Also, avoid constructing trace messages outside of conditional guard statement. For example, the code in Example 3-1 creates a large string object even if tracing is disabled.

Example 3-1 Creating a large string object

String boTrace = bo.toString();

Although this pattern is always inefficient, it impacts performance even more if the BO size is large. To avoid unnecessarily creating a BO when tracing is disabled, move the string construction inside an if statement, as shown here:

if (tracing on) System.out.println(bo.toString());

## Avoiding buffer-doubling code

Study the memory implications of using Java data structures that expand their capacity based on input (for example, StringBuffer and ByteArrayOutputStream). Such data structures usually double their capacity when they run out of space. This doubling can produce significant memory pressure when processing large objects. If possible, always assign an initial size to such data structures.

# 3.2.12 Mediation Flow Component considerations

This section describes Mediation Flow Component (MFC) considerations for performance.

# Using Extensible Stylesheet Language Transformation (XSLT) primitives versus business object maps

The XSLT primitive offers two alternate transformation approaches in a mediation flow. If no XSLT-specific function is required, then it is generally better to use the Business Object Map primitive, which can be faster. The exception is when a Mediation Flow Component is trivial in nature and the transformation is taking place at the /body level of the service message object (SMO). In this case, XSLT is faster because the native XML bytes can be passed straight to the XSLT engine. Native XML bytes are available if the XSLT transform primitive is the first in the flow or only preceded by one or more of the following primitives:

- ► Route on Message Header (Message Filter primitive)
- ► XSLT primitive (Transforming on /body as the root)
- ► EndpointLookup without Xpath user properties.
- Event emitter (event header only)

In Business Process Manager 8.0, the Integration Designer enhances the XML Mapper to use Business Object Maps for more cases, which results in better runtime performance. This enhancement is described further in the presentation at the following location:

http://publib.boulder.ibm.com/infocenter/ieduasst/v1r1m0/topic/com.ibm.iea.iid/iid/8.0/EnhancementsOverview/BPM80 IID Enhancements.pdf

# Aggregation blocks (FanOut and FanIn)

Aggregation is an important MFC pattern. It enables a single inbound request to map into multiple outbound service invocations, the responses from which can be aggregated into a single response to the original request. Before you develop mediations using aggregation design patterns, you need to consider several performance factors. See the developerWorks topic about best practices, "Aggregation design patterns and performance considerations in WebSphere Enterprise Service Bus V7.5" at the following location:

http://www.ibm.com/developerworks/websphere/library/techarticles/1111\_norris/1111\_norris.html

# **Configuring Mediation Flow Component resources**

When creating resources using Integration Designer, the application developer might choose to use preconfigured MFC resources or let the tool generate the mediation flow-related resources that it requires. Both approaches have their advantages and disadvantages.

Preconfigured resources help in the following circumstances:

- Existing resources are to be used
- External creation and tuning scripts are to be applied

Preconfigured resources also allow easier post-deployment adjustment.

Tooling-created resources are suitable if no further need exists for creating resources using scripts or the administrative console. Most performance tuning options can be changed because they are now exposed in the tooling.

In our performance tests, we used preconfigured resources because segregating the performance tuning from the business logic makes it possible to maintain the configuration for different scenarios in a single script.

# 3.3 Browser environment considerations

When using a browser for developing or evaluating Business Process Manager client solutions through the Process Portal or Business Space, developers often alter the configuration of the browser to perform debugging, tracing, and other browser functions. However, some of these configuration changes can dramatically affect the performance of the Business Process Manager solution. Before rolling out a solution to production or obtaining performance measurements, review this section and observe its guidelines.

## Disable or uninstall add-ins or extensions for production use

An important consideration is using add-ins or extensions for your browser environment. If you experience performance problems while using the browser, make sure you disable or uninstall all add-ins or extensions unless they are necessary.

#### Avoid Developer Tools render or compatibility mode in Internet Explorer

In Internet Explorer (IE), placing the browser in compatibility mode or in a render mode equivalent to an older browser version by using the Developer Tools is possible. This option can be useful for developing or debugging solutions (for example, making an IE 8 browser behave as an IE 7 browser for compatibility testing). However, make sure that you do not use these settings in production.

## Using browser tools

The following observations pertain to browser tools that are available for obtaining response time measurements, counting requests, and analyzing caching.:

- ► The Net tab in Firebug is useful for obtaining request timings, analyzing request/response headers, and counting the number of requests. However, it reports requests that are satisfied from the browser cache as code 200 responses. You can still determine that the request is cached from the Cache tab shown on the request, which indicates that the request was satisfied from the browser cache. If you copy and paste the results into another document (for example, into an email), the Cache tab is not copied. Thus, it is possible to be misled by the 200 responses and draw an incorrect conclusion that caching is not effective when it actually is.
- ► Fiddler is another powerful tool and has the advantage of supporting both IE and Firefox browsers. However, because Fiddler acts as a proxy between the browser and the server and cached requests are handled internally by browsers, these requests are never shown in Fiddler. This absence of result reporting prevents you from determining which requests are fulfilled from the browser cache, but Fiddler is still useful for analyzing the requests that actually are sent to the server.
- ► HttpWatch does not have the limitations of Fiddler because it is supported on both IE and Firefox browsers. Its results copy and paste easily into either a spreadsheet or a document, and it displays cached requests in a straightforward manner.

# 3.4 WebSphere InterChange Server migration considerations

The following considerations pertain to those migrating from WebSphere InterChange Server (WICS) to Business Process Manager V8.0:

- Migrated workloads using custom IBM WebSphere Business Integration (WBI) adapters or older WebSphere Business Integration adapters result in interaction with Business Process Manager V8.0 through JMS, which is slower than the JCA adapters. Use WebSphere adapters to replace WebSphere Business Integration adapters when possible.
- ► Some technology adapters (such as HTTP and web services) are migrated by the WebSphere InterChange Server migration wizard into native Business Process Manager V8.0 SCA binding, which performs better. For adapters that are not migrated automatically to available SCA bindings, development effort spent on migrating manually to an SCA binding removes the dependency on an older adapter and provides better performance.
- ► The WebSphere InterChange Server Migration wizard in Integration Designer offers a feature to merge the connector and collaboration module. Enable this option, if possible, because it increases performance by reducing cross-module SCA calls.
- WebSphere InterChange Server collaborations are migrated into Business Process Manager V8.0 BPEL processes. You can further customize the resultant BPEL processes so they become more efficient.

- The generated BPEL flows still use the WICS APIs to perform BO and collaboration-level tasks. Development effort spent cleaning up the migrated BPEL to use Business Process Manager APIs instead of the ICS APIs results in better performance and better maintainability.
- You might be able to replace BPEL processes produced by migration with other artifacts. All WebSphere InterChange Server collaborations are currently migrated into BPEL processes. For certain scenarios, other Business Process Manager server artifacts (for example, business rules) might be better choices. Investigate the BPEL processes produced by migration to ensure that the processes are the best fit for your scenario.
- ▶ Disable Message Logger calls in migration-generated Mediation Flow Components (MFCs). The WebSphere InterChange Server Migration wizard in Integration Designer generates an MFC to deal with the mapping details of a connector. This MFC contains the code for handling synchronous and asynchronous calls to maps that transform application-specific BOs to generic BOs and generic BOs to application-specific objects.
  - The generated MFC contains embedded MessageLogger calls that log the message to a database. Disable these calls if they are not required in your business scenario to reduce writes to the database and thus improve performance. (Select the MessageLogger instance, choose the Details panel, and clear the **Enabled** check box.)
- ▶ Reduce memory pressure by splitting the shared library generated by the migration wizard. The migration wizard creates a single shared library and puts all migrated BOs, maps, and relationships into it. All the migrated modules share this library by copy. This sharing can cause memory bloat for cases where the shared library is large and many modules are present. The solution is to manually refactor the shared library into multiple libraries based on functionality or usage and modify modules to reference only the shared libraries that they need.
- If the original WebSphere InterChange Server maps contain many custom map steps, the development effort spent in rewriting those map steps results in better performance. The WebSphere InterChange Server Migration wizard in Integration Designer V8.0 generates maps that use the ICS APIs at a translation layer above Business Process Manager V8.0 server technologies. Removing this layer by making direct use of Business Process Manager V8.0 server APIs avoids the cost of translation and produces better performance.

# Performance tuning and configuration

To optimize performance, it is necessary to configure a system differently than the default settings. This chapter lists several areas to consider during system tuning, including Business Process Manager products and other products in the system, such as DB2. Documentation for each of these products can answer questions about performance, capacity planning, and configuration and offers guidance about achieving high performance in various operational environments.

Several configuration parameters are available to the system administrator. Although this chapter identifies several specific parameters observed to affect performance, it does not address all available parameters. For a complete list of configuration parameters and possible settings, see the relevant product documentation.

The first section of this chapter offers a methodology for tuning a deployed system. Following this section is a basic tuning checklist that enumerates the major components and their associated tuning parameters. Subsections follow the checklist that address tuning in more detail, describing several tuning parameters and their suggested settings (where appropriate) and providing advanced tuning guidelines for key areas of the system. Representative values for many tuning parameters are shown in Chapter 5, "Initial configuration settings" on page 97.

**Important:** There is no guarantee that following the guidance in this chapter will provide acceptable performance for your application. However, if you set these parameters incorrectly, you can expect degraded performance.

"Related publications" on page 107 contains references to related documentation that might prove valuable when tuning a particular configuration.

# 4.1 Performance tuning methodology

We suggest a system-wide approach to performance tuning the Business Process Manager environment. System performance tuning, which requires training and experience, is not exhaustively described here. Rather, we highlight key aspects of tuning that are important.

Tuning encompasses every element of the deployment topology:

- Physical hardware topology choices
- Operating system parameters
- ► Business Process Manager server, WebSphere Application Server, database, and messaging engine settings

The methodology for tuning can be stated as an iterative loop:

- 1. Pick a set of reasonable initial parameter settings and run the system.
- 2. Monitor the system to obtain metrics that indicate where performance is being limited.
- 3. Use monitoring data to guide further tuning changes.
- 4. Repeat until done.

These steps are described next.

# 4.1.1 Picking a set of reasonable initial parameter settings

Use the tuning checklist in 4.2, "Tuning checklist" on page 50 for a systematic way to set parameters.

For specific initial values, see Chapter 5, "Initial configuration settings" on page 97 for settings of the workloads that are used in IBM internal performance evaluation. You might consider these values for initial values.

# 4.1.2 Monitoring the system

Monitor the system components to determine system health and the need for further tuning as follows:

- For each physical machine in the topology, including front-end and back-end servers such as web and database servers, monitor the following processes by using the relevant OS tools (such as **vmstat**, **iostat**, **netstat**, or their operating system-specific equivalents):
  - Processor core use
  - Memory use
  - Disk use
  - Network use
- Complete the following actions for each Java virtual machine (JVM) process started on a physical machine (for example, process server, messaging engine server, and other components):
  - Use tools such as ps or their equivalents to get core and memory usage per process.
  - Collect verbose garbage collection (verbosegc) statistics to obtain information about Java memory usage.

- ► For each Business Process Manager server or messaging engine JVM, use a tool such as IBM Tivoli® Performance Viewer, or the WebSphere Performance Tuning Toolkit, to monitor these types of data:
  - Data connection pool use for each data source
  - Thread pool use for each thread pool (web container, default, and Work Managers)

You may download the WebSphere Performance Tuning Toolkit from this location:

http://www.ibm.com/developerworks/websphere/downloads/peformtuning.html

▶ Monitor the database systems, which includes the databases for the Process Center, Process Server, Performance Data Warehouse, Business Monitor, and any other applications that are part of the Business Process Manager solution. Business Process Manager solutions are often database-intensive, so ensuring excellent performance for the databases is critical. Use the database vendor's monitoring tools, along with operating system tools such as iostat, vmstat, or the equivalent.

# 4.1.3 Use monitoring data to guide further tuning changes

Correctly using monitoring data to determine how to tune the Business Process Manager requires skill and experience. In general, this phase of tuning requires the analyst to look at the collected monitoring data, detect performance bottlenecks, and do further tuning. The key characteristic of this phase of tuning is that it is driven by the monitoring data that is collected in the previous phase.

Performance bottlenecks include, but are not limited to, these situations:

- ► Excessive use of physical resources, such as processor cores, disk, and memory. These issues can be resolved either by adding more physical resources or by rebalancing the load across the available resources.
- ► Excessive use of virtual resources. Examples of these resources include heap memory, connection pools, thread pools, and other resources. In this case, use tuning parameters to remove the bottlenecks.

# 4.1.4 Information required to diagnose and resolve performance issues

Several sources of information are highly valuable, even necessary, when diagnosing and resolving performance problems. This information is often referred to as *must-gather information*. It includes the following items:

- ► Client (Process Designer or Portal) CPU utilization (for example vmstat)
- ▶ Process Center or Process Server CPU utilization
- Database server CPU, disk subsystem (for example iostat), and network utilization; also, for Oracle, the AWR Report
- ► The verbosego logs (even if this problem is not a memory problem)
- SystemOut and SystemErr logs
- ► The contents of the configuration directory for the active profile of the server being studied, for example, the following location:

profile\_dir/config/cells/cellName/nodes/nodeName/servers/serverName

This information is useful for obtaining a system view of performance, and often pinpoints the area that needs a more detailed examination. Additional diagnostic information for common performance bottlenecks are as follows:

- ► For a hang or unusually slow response time:
  - A series of javacore files (3 5 dumps, separated by 30 seconds or a few minutes)
  - Characterization of the network latency between key components of the system
     From client to server:
    - Between Process Designer and Process Center
    - · Between Process Designer and Process Server
    - From Portal to Process Server

From server to database:

- Between Process Center and the Process Center database
- Between Process Server and the Process Server database
- ► For memory failures (OutOfMemory):
  - heapdump data (phd) from the time of the memory failure
  - javacore from the time of the memory failure
- ► For a suspected memory leak:
  - A series of heapdump files (PHD files) taken at different times before the out-of-memory exception
  - If the issue also presents itself as unusually slow response times, it might be more
    effective to analyze it that way (that is, gather the data listed under this category)
- ► For database performance issues:
  - SQL traces
    - Statement Monitor for DB2

http://www.ibm.com/developerworks/data/library/techarticle/0303kolluru/03 03kolluru.html

· SQL Trace for Oracle

http://www.orafaq.com/wiki/SQL\_Trace

# 4.2 Tuning checklist

This checklist serves as a guide when tuning a Business Process Manager solution. Each topic is covered in more detail in the remainder of this chapter.

- ► Common tunables
  - Use a 64-bit JVM for all servers.
  - Disable tracing, logging, and monitoring when possible.
  - Database performance is crucial for all Business Process Manager solutions, so ensure that all databases are well-tuned. For example, use a minimum of 2 GB for buffer pools or cache sizes, place logs and containers on separate physical disk subsystems, and define appropriate indexes. Further information is provided in sections later in this chapter.
  - If security is required, use application security, not Java2 security.

- Use an appropriate hardware configuration for performance measurement (for example, notebooks and desktops are not appropriate for realistic server performance evaluations).
- If hardware virtualization is used, ensure that adequate processor, memory, and I/O resources are allocated to each virtual machine. Avoid overcommitting resources.
- Minimize network latency, and ensure sufficient network bandwidth, between all systems in the configuration, which includes the following items:
  - Between the Process Portal clients and the Process Server
  - · Between the Process Server and its databases
  - Between the Process Designer clients and the Process Center
  - · Between the Process Center and its database
- Do not run production servers in development mode or with a development profile.
- Tune external service providers and external interfaces to ensure that they do not cause a system bottleneck.
- Configure message-driven bean (MDB) activation specifications.
- Configure for clustering, where applicable).
- Configure thread pool sizes.
- Configure settings of data sources for connection pool size and prepared statement cache size. Consider using non-XA data sources for Common Event Infrastructure data when that data is non-critical.
- Increase the maximum number of connections in the data pool to greater than or equal to the sum of all maximum thread pool sizes.
- Business Processing Modeling Notation (BPMN) business processes
  - Set bpd-queue-capacity to 10 times number of physical processors, capped at 80.
  - Set the max-thread-pool size to 30 plus 10 times the number of physical processors, capped at 110.
  - Increase log file size for the Process Server database to 16,384 pages.
  - Enable file system caching for the Process Server database:
    - db2 alter tablespace userspace1 file system caching
  - Exclude the table SIBOWNER from automatic runstats execution.
  - Ensure that database statistics are up to date.
- Business Process Choreographer (for BPC business processes)
  - Use Work Manager-based navigation for long running processes, and optimize the message pool size and intertransaction cache size.
  - Use query tables to optimize query response time.
  - Optimize Business Flow Manager resources:
    - Database connection (Business Process Choreographer database)
    - Activation specification (BPEInternalActivationSpec)
    - Java Message Service (JMS) data source connection (BPECF and BPECFC)
  - Optimize the database configuration for the Business Process Choreographer database (BPEDB).
  - Optimize indexes for SQL statements that result from task and process list queries using database tools such as the DB2 design advisor.
  - Turn off state observers that are not needed (for example, audit logging).

## Messaging and message bindings

- Optimize activation specification (JMS, MQJMS, WebSphere MQ).
- Optimize queue connection factory (JMS, MQJMS, WebSphere MQ).
- Configure connection pool size (JMS, MQJMS, WebSphere MQ).
- Configure service integration bus data buffer sizes.

#### Database

- Place database table spaces and logs on a fast disk subsystem.
- Place logs on a separate device from the table space containers.
- Maintain current indexes on tables.
- Update database statistics.
- Set log file sizes correctly.
- Optimize buffer pool size (DB2) or buffer cache size (Oracle). For example, if file system caching is disabled (the is, direct I/O), set the buffer pool/cache size to at least 2 GB.

#### Java

- Set the heap and nursery sizes to manage memory efficiently.
- Choose the appropriate garbage collection policy (generally, -Xgcpolicy:gencon).
- Enable verbosegc to obtain Java memory statistics for later analysis. There is essentially no overhead attributable to enabling verbosegc.

#### ▶ Business Monitor

- Configure Common Event Infrastructure.
- Set message consumption batch size.
- Enable key performance indicator (KPI) caching.
- Use table-based event delivery.
- Enable the data movement service.

# 4.3 Common tuning parameters

This section lists performance tuning parameters commonly used for tuning Business Process Manager solutions, for both BPMN and BPEL business processes.

# 4.3.1 Tracing and logging flags

Tracing and logging are often necessary when setting up a system or debugging issues. However, these capabilities require performance resources that are often significant. Minimize their use when evaluating performance or in production environments. This section lists tracing parameters used in the products covered in this paper. Some settings are common to all or a subset of the products; others are specific to a particular product. Unless stated otherwise, you can set all of these parameters using the administrative console.

To enable or disable tracing, click **Troubleshooting**  $\rightarrow$  **Logs and Trace** in the properties of the subscription. Select the server on which you want to change the log detail levels and click **Change Log Detail Levels**. Set both the **Configuration** and **Runtime** fields to the following value:

\* =all=disabled

To change the Performance Monitoring Infrastructure (PMI) level, click **Monitoring and Tuning**  $\rightarrow$  **Performance Monitoring Infrastructure**. Select the server on which you want to change the log detail levels and click **none**.

In addition, Cross-Component Tracing (XCT) is useful for problem determination, enabling correlation of Service Component Architecture (SCA) component information with log entries. However, do not use XCT in production or while obtaining performance data. Two levels of XCT settings are possible:

- ▶ Enable
- ► Enable with data snapshot

Both incur significant performance resource usage. Enable with data snapshot is costly because of the additional I/O involved in saving snapshots in files.

To enable or disable XCT, click **Troubleshooting**  $\rightarrow$  **Cross-Component Trace**. Select the **XCT** setting from three options under the Configuration or Runtime tab:

- ► Enable
- ▶ Disable
- ► Enable with data snapshot

Changes made on the Runtime tab take effect immediately. Changes made on the Configuration tab require a server restart to take effect.

Further information is provided in the "Managing Log Level Settings in TeamWorks" technote:

http://www.ibm.com/support/docview.wss?uid=swg21439659

# 4.3.2 Java memory management tuning parameters

This section lists several frequently used Java virtual machine (JVM) memory management tuning parameters. For a complete list, see the JVM tuning guide offered by your JVM supplier.

To change the JVM parameters, complete the following steps:

- Go to the JVM administrative window by first clicking Servers → Application → Performance Monitoring Infrastructure.
- 2. Select the server on which you want to change the JVM tuning parameters.
- 3. Click Server Infrastructure  $\rightarrow$  Java and Process Management  $\rightarrow$  Process Definition  $\rightarrow$  Additional Properties  $\rightarrow$  Java Virtual Machine.
- 4. Change the JVM parameters on this panel.

# Java garbage collection policy

The default garbage collection (GC) algorithm on platforms with an IBM JVM is a generational concurrent collector (specified with **-Xgcpolicy:gencon** under the Generic JVM arguments on the JVM administrative console panel). Our internal evaluation shows that this garbage collection policy usually delivers better performance with a tuned nursery size, as described in the next section.

# Java heap sizes

To change the default Java heap sizes, set the initial heap size and maximum heap size explicitly on the JVM window in the administrative console. The 64-bit JVMs (the suggested mode for Business Process Manager servers) support much larger heap sizes than 32-bit JVMs. Use this capability to relieve memory pressure in the Java heap, but always ensure that there is sufficient physical memory to back the JVM heap size and all other memory requirements.

If you click **Generational Concurrent Garbage Collector**, the Java heap is divided into a new area (*nursery*), where new objects are allocated, and an old area (*tenured space*), where longer-lived objects are located. The total heap size is the sum of the new area and the tenured space. You can set the new area size independently from the total heap size. Typically, set the new area size in the range of 1/4 and 1/2 of the total heap size. The relevant parameters are as follows:

- ► Initial new area size: Xmns<size>
- ► Maximum new area size: Xmnx<size>
- ► Fixed new area size: Xmn<size>

# 4.3.3 Message-driven bean ActivationSpec

To access the MDB ActivationSpec tuning parameters, more than one shortcut is available in the administrative console:

- ► Click Resources → Resource Adapters → J2C activation specifications. Select the name of the application specification you want to access.
- Click Resources → Resource Adapters → Resource adapters. Select the name of the resource adapter you want to access. Then click Additional properties → J2C activation specifications. Select the name of the activation specification you want.

The following custom properties in the ActivationSpec message-driven bean (MDB) have considerable performance implications. These properties are described further in "Tuning message-driven bean ActivationSpec properties" on page 64.

- maxConcurrency
- maxBatchSize

# 4.3.4 Thread pool sizes

Business Process Manager servers use thread pools to manage concurrent tasks. You can set the Maximum Size property of a thread pool in the administrative console by clicking **Servers**  $\rightarrow$  **Application servers** and selecting the server name whose thread pool you want to manage. Click **Additional Properties**  $\rightarrow$  **Thread Pools** and then the thread pool name.

You typically must tune the following thread pools:

- Default
- ► ORB.thread.pool
- ▶ WebContainer

In addition, thread pools that are used by Work Managers for BPEL processes are configured separately in the console by clicking **Resources**  $\rightarrow$  **Asynchronous beans**  $\rightarrow$  **Work managers**. Select the Work Manager name and then click **Thread pool properties** 

You typically must tune the following Work Managers:

- ▶ DefaultWorkManager
- ▶ BPENavigationWorkManager

# 4.3.5 Java Message Service connection pool sizes

You can access the JMS connection factories and JMS queue connection factories from the administrative console in several ways:

- ► Click Resources → Resource Adapters → J2C connection factories and select the factory name.
- ► Click **Resources** → **JMS** → **Connection factories** and select the factory name.
- ► Click Resources → JMS → Queue connection factories and select the factory name.
- ► Click Resources → Resource Adapters → Resource adapters and select the resource adapter name (for example, SIB JMS Resource Adapter). Then click Additional priorities → J2C connection factories and select the factory name.
- ► From the connection factory admin panel, click **Additional Properties** → **Connection pool properties**. Set the **Maximum connections** property for the maximum size of the connection pool.

# 4.3.6 Java Database Connectivity data source parameters

Data sources can be accessed through either of these paths:

- ► Click **Resources** → **JDBC** → **Data sources** and select the data source name.
- ► Click **Resources** → **JDBC Providers** and select the Java Database Connectivity (JDBC) provider name, followed by clicking **Additional Properties** → **Data sources** and selecting the data source name.

# **Connection pool size**

The maximum size of the data source connection pool is limited by the value of the Maximum connections property, which can be configured by clicking the **Additional Properties**  $\rightarrow$  **Connection pool properties** in the data source window.

Increase the maximum number of connections in the data pool to greater than or equal to the sum of all maximum thread pool sizes.

The following data sources typically must be tuned:

- ► Business Process Choreographer (BPC) data sources for the BPEDB and associated message engine database (for BPEL business processes)
- ► BPMN data sources for the BPMN databases and associated message engine databases (for BPMN business processes)
- ► SCA application bus messaging engine data source
- ► SCA system bus messaging engine data source
- ► Common Event Infrastructure (CEI) bus messaging engine data source

#### Prepared statement cache size

You can configure the cache size of the data source prepared statement from the data source. Click **Additional properties**  $\rightarrow$  **WebSphere Application Server data source properties**.

For BPEL business processes, ensure that each data source's prepared statement cache is sufficiently large. For example, set the BPEDB data source prepared statement cache size to at least 300.

# 4.3.7 Messaging engine properties

Two messaging engine custom properties might affect the messaging engine performance:

- sib.msgstore.discardableDataBufferSize
  - The property stays in the data buffer for best effort nonpersistent messages.
  - The default value is 320 KB.
  - After the buffer is full, messages are discarded to allow newer messages to be written to the buffer.
- sib.msgstore.cachedDataBufferSize
  - The property stays in memory cache for messages other than best-effort nonpersistent.
  - The default is 320 KB.

To access these properties in the console, use the following steps:

- 1. Click **Service Integration** → **Buses** and select the bus name.
- 2. Click **Messaging Engines** and select the messaging engine name.
- 3. Click Additional properties → Custom properties.

# 4.3.8 Running production servers in production mode

Business Process Manager servers can be run in development mode to reduce startup time for the server by using JVM settings to disable bytecode verification and reduce just-in-time (JIT) compilation time. Do not use this setting on production servers because it is not designed to produce optimal runtime performance. Make sure to clear the **Run in development mode** check box for the server. This setting is found in the configuration window of the server in the administrative console. Click **Servers**  $\rightarrow$  **Application Servers**. Click the server whose setting you want to change and click **Configuration**.

You might also create server profiles with production or development templates. Use production profile templates for production servers.

# 4.4 Process Portal tuning and usage

This section contains tuning advice and usage guidelines for the Process Portal.

# 4.4.1 Using a high-performing browser

The choice of browser technology is crucial to Process Portal performance. In some cases, more recent versions of the browser will perform much better than older versions.

# 4.4.2 Enable browser caching

Browsers generally cache static data after it is initially retrieved from the server, which can significantly improve response time for scenarios after the cache is primed. This improvement is especially true for networks with relatively high latency. Ensure that the browser cache is active and is effective. Note that cache settings are browser-specific; see 4.11, "Enable browser caching" on page 78 for further details.

# 4.4.3 Locate the Process Portal physically close to the Process Server

One factor that influences network latency is the physical distance between systems. Where practical, locate Business Process Manager V8.0 servers physically close to each other and to the Process Portal users to minimize the latency for requests.

# 4.4.4 Use the WORK tab to refresh the Task List

Instead of refreshing the entire Process Portal browser page through F5 or a similar mechanism, click the WORK tab on the Process Portal browser page. This way refreshes only the tasks in the task list, and not refresh the entire browser page.

# 4.4.5 Use modern desktop hardware

For many Business Process Manager solutions, much of the processing is done on the client system (for example browser rendering). Therefore, be sure to deploy modern desktop hardware with sufficient physical memory and high-speed processors with large caches and fast front-side buses. Monitor your client systems with performance tools (Windows Task Manager or vmstat) to ensure that the client system has sufficient processor and memory resources to yield high performance.

## 4.4.6 Disable or uninstall add-ins or extensions

An important consideration is using add-ins or extensions in your browser. If you experience problems, always disable or uninstall all add-ins or extensions unless they are necessary.

# 4.5 Business Processing Modeling Notation business process tuning

In addition to the common tuning guidance, this section provides tuning guidance that is specific to BPMN business processes. Much of this tuning applies to the Performance Server and the Performance Server's database.

#### 4.5.1 Tune the Process Server Database

The following list indicates the ways that databases can be tuned for better performance. In addition to these items, see 4.13, "General database tuning" on page 80 and vendor-specific database tuning sections (4.14, "DB2-specific database tuning" on page 82 and 4.15, "Oracle-specific database tuning" on page 88).

- ► Increase log file size for the Process Server database to 16,384 pages.
- Enable file system caching for the Process Server database as follows (this example is for DB2):
  - db2 alter table space userspace1 file system caching
- ► Exclude the table SIBOWNER from automatic runstats execution as described in the following technote:

http://www.ibm.com/support/docview.wss?uid=swg21452323

- ► Ensure that database statistics are the most current.
  - If database utilization is running at high throughput rates, consider disabling some or all database auto-maintenance tasks to avoid impacting peak throughput. However, if you disable these capabilities, be sure to perform runstats regularly to update database statistics.
- ▶ Use your database vendor's tool to obtain recommendations for indexes to create; this step is necessary because different applications often require unique indexes. Create the indexes that are suggested by the database vendor's tool.

# 4.5.2 Tune the Event Manager

This section offers tuning suggestions for the Event Manager.

# Tune BPD queue size and worker thread pool size

To optimize throughput and scaling, a necessary step is often to set the BPD Queue Size and Worker Thread Pool parameters to larger values than their defaults. These values are defined in the file 80EventManager.xml file in the configuration directory for the Process Server. The specific configuration directory is as follows:

%BPM%/profiles/<profileName>/config/cells/<cellName>/nodes/<nodeName>/servers/server1/process-center or process-server/config/system

To change the values, directly edit that file. Here are several guidelines for tuning these parameters:

- ► Start with a BPD Queue Size (bpd-queue-capacity) of 10 per physical processor core (for example, 40 for a four-processor core configuration), with a maximum value of 80. Tune as needed after that, based on the performance of your system.
- ► Start with a Worker Thread Pool Size (max-thread-pool-size) of 30 + 10 per physical processor core (for example, 70 for a four-processor core configuration), with a maximum value of 110. Tune as needed after that, based on the performance of your system.

#### **Tune the Number of Timer Events**

For BPDs with many timers, reduce the amount of Event Manager activity by reducing the number of timer events that are held in memory through the following change to the 80EventManager.xml file in the profiles directory (the full path to this file is in "Tune BPD queue size and worker thread pool size" on page 58); the default is 60000:

<loader-advance-window>5000</loader-advance-window>

# 4.5.3 Optimize business data search operations

If slow response times, or high database usage, are observed when performing business data searches, do the following tasks:

- ► Ensure that no more than 10 business data variables are defined. If there are more than 10 of these variables, examine your business requirements to determine if all the variables are required. Our experience shows that 10 or less is generally sufficient.
- ► Enable Process Search optimizations through the Saved Search Accelerator Tools for the Process Server. This technique is often much faster, and uses fewer database resources, than the default mechanism. The Process Search optimizations can be enabled by using command-line tools, as described at the following location:

http://pic.dhe.ibm.com/infocenter/dmndhelp/v8r0m1/index.jsp?topic=%2Fcom.ibm.wbpm.main.doc%2Ftopics%2Fctuneprocportal.html

# 4.5.4 Tune Participant Groups

For participant groups with many users, if you are not using the external email capability (which is enabled by default), turn it off through the following change to 99Local.xml in the profiles directory:

<send-external-email>false</send-external-email> (default is true)

This step reduces load on the Process Server and its database by eliminating unnecessary email lookups.

# 4.5.5 Utilize a fast disk subsystem on the Process Server cluster members

In addition to using a fast disk subsystem (for example a RAID adapter with 10 or more physical disks) for databases, using a fast disk subsystem on the Process Server cluster members (App Targets) is also essential. Several disk I/O operations are performed directly on the Process Server system, including compensation logging, transaction logging, profile operations (that is, Administrative activities), and maintaining the Lucene Task Search indexes.

# 4.5.6 Remove unnecessary snapshots from the Process Server

Over time, unused snapshots can accumulate on the Process Server. This can be the result of many factors, including iterative development resulting in unused snapshots as new versions of a solution are deployed, and obsolete snapshots that were part of a development cycle and were never removed when the solution went into production. These unused snapshots can degrade performance, particularly if they contain Advanced Content. Business Process Manager 8.0.1 added a new utility, BPMDeleteSnapshot, to remove unnecessary snapshots from the Process Server. Read more at the following link:

http://pic.dhe.ibm.com/infocenter/dmndhelp/v8r0m1/index.jsp?topic=%2Fcom.ibm.wbpm.ref.doc%2Ftopics%2Frref\_deletesnapshot.html

In addition to this information, perform periodic maintenance on the snapshots that are deployed on the Process Server. This maintenance includes deleting unused Process Applications and Toolkits, and archiving unneeded snapshots.

# 4.5.7 Disable notifications if they are not required

When running at high throughput rates the overhead of processing notifications can become a Process Server scaling bottleneck. Specifically, the PortalNotificationTopicSpace can become contended and overrun (notifications can be lost). If notifications are not a business requirement, they can be turned off by setting the following value in the 99Local.xml file in the appropriate profile subdirectory; this step eliminates the bottleneck previously described:

<push-notifications enabled="false">

# 4.5.8 Define Authentication Alias when using CEI to emit events

If you have BPDs that use CEI to emit business monitoring events, define the authentication alias for the CEI service integration bus. It is not defined by default, which causes time-consuming authentication checks to fail repeatedly.

To set the authentication alias, edit <code>OOStatic.xml</code> in the profiles directory and change <code>MonitorBusAuth</code> to the correct authentication alias for the CEI service integration bus in the following stanza:

```
<monitor-event-emission>
...
<!-- Provide either the j2c-authentication-alias or jms-auth property JMS connections
require authentication. -->
<j2c-authentication-alias-name>MonitorBusAuth</j2c-authentication-alias-name>
```

# 4.5.9 Tune cache parameters

Several cache settings can be changed through configuration parameters in the following XML configuration files in the profiles directories:

- ► 00Static.xml
- ► 99Local.xml
- ► 100Custom.xml

Values can be changed in 00Static.xml, but for some installations a preferable approach for upgrade safety is to make such modifications in 100Custom.xml to override the defaults.

Configuration files are read during server startup so changes will require a server restart. The parsed output is written to the TeamworksConfiguration.running.xml file during server startup. Therefore, to validate that your expected configuration changes actually are being used, confirm the value in this TeamworksConfiguration.running.xml file.

**File is rebuilt at each startup:** Making changes in TeamworksConfiguration.running.xml has no effect, because this file is rebuilt on each server startup.

#### Process Server cache tuning

Several cache settings that might benefit from larger values in a production Process Server, as distinct from the development Process Center.

One setting is the Time To Live setting:

```
<cached-objects-ttl>0</cached-objects-ttl>
```

The value of zero is entirely appropriate for a Process Center where development work is active and you want the changes to objects such as coaches to reflect updates immediately. However in a runtime Process Server, the deployment model generally means that changes to coaches are comparatively rare.

In a production Process Server system increase the value, as shown in the following example. This value changes the Time To Live to 300 seconds.

```
<cached-objects-ttl>300</cached-objects-ttl>
```

If snapshot deployments are rare, this value can be increased to 24 hours by using the following setting:

```
<cached-objects-ttl>86400</cached-objects-ttl>
```

Restarting the Process Server clears the caches so if code is deployed and it is required that the change is recognized immediately, the Process Server can be restarted, or the PO cache can be reset through the Process Admin console under the Manage Caches link.

A related configuration setting is the number of objects in the cache. Two configuration flags in 00Static.xml file can manage this value:

- <default-unversioned-po-cache-size>500</default-unversioned-po-cache-size>
- <default-versioned-po-cache-size>500</default-versioned-po-cache-size>

For low volume environments with relatively few process applications and coaches, this value may be sufficient. However, for more complex environments with many process applications or coaches, increase this value so that the process applications and coaches are held in the cache of their initial use. This step can improve response time when accessing these process applications and coaches. For example, increase each of these values to 1500.

When the cache is "cold" after a restart, initial coach load times might take longer until the cache is populated.

The effectiveness of these caches can be monitored through the Instrumentation Page in the Process Admin console, which indicates how many cache hits and misses occurred. For more detailed analysis, obtain Instrumentation logs from this page, and which can be analyzed by IBM Support through a PMR to determine whether further cache-size increases are warranted.

The UCP column in the Manage Caches page of the Process Admin console can also be used to monitor how effectively the cache is working for a particular runtime server. The Process Admin console has online help that describes the column headings and their meanings.

User group membership information is also stored in a cache so a company with a large LDAP user and group population may require a larger setting for LDAP caches to avoid a performance impact when user/group information is accessed, such as during authorization validation for task assignment, login to Process Portal, or refreshing the Task List in Process Portal.

#### Cache settings for memory-constrained environments

In a memory-constrained environment, such as when using a 32-bit JVM, a beneficial approach might be to reduce the size of some caches. An example is the number of snapshots that are cached for a single branch in the Process Center. For very large process applications, reducing this value can reduce JVM heap memory usage. Reduce the following value to accomplish this goal:

<snapshot-cache-size-per-branch>64</snapshot-cache-size-per-branch>

Similarly, for a Process Server in a memory-constrained environment, reducing the Branch Manager cache size can reduce heap memory for large process apps. The Branch Manager cache contains metadata about the contents of snapshots in memory, and is used to improve performance of certain operations. It is controlled by the configuration flag:

<branch-context-max-cache-size>64/branch-context-max-cache-size>

The default value is 64. If process applications are particularly large, reducing this value might be necessary, particularly for runtime servers where a new branch is created for each deployed snapshot.

# 4.6 Process Center tuning

Because all Process Designer users access the Process Center, and for many cases use a significant number of resources on the Process Center (and its database), optimizing its configuration is essential. At a minimum, tune the Process Center in the following ways:

- ► Ensure there is a high-bandwidth, low-latency network connection between Process Designer users and the Process Center, and the Process Center and its database.
- Use a 64-bit JVM.
- Use the generational concurrent garbage collector through the following argument:
  - -Xgcpolicy:gencon JVM
- ► Ensure that the Java heap size is sufficiently large to handle the peak load. For more information about setting the Java heap size, see 4.3.2, "Java memory management tuning parameters" on page 53
- ► Set the object request broker (ORB) thread pool size to at least 50.
- ► Set the maximum Java Database Connectivity (JDBC) connections for the Process Server data source (jdbc/TeamWorksDB) to at least double the maximum number of threads in the ORB thread pools for each node in the cell. For example, if two Process Center nodes exist, and the ORB service thread pool of each node is set to a maximum of 50 threads, set the Process Server data source to accept at least 200 connections.
- ► Tune the Process Center database. For example, ensue the buffer pool or cache size is at least 2 GB. For more information, see 4.13, "General database tuning" on page 80.

# 4.7 Advanced tuning

This section describes various advanced tuning tips.

# 4.7.1 Tracing and monitoring considerations

The ability to configure tracing and monitoring at different levels for various system components is valuable during periods of system analysis or debugging. The Business Process Manager product set provides rich monitoring capabilities, both in terms of business monitoring through the CEI and audit logging, and system performance monitoring through the PMI and the Application Response Measurement (ARM) infrastructure. Although these capabilities provide insight into the performance of the running solution, these features can degrade overall system performance and throughput.

**Tracing and monitoring effect on performance:** Use tracing and monitoring judiciously. When possible, turn off all non-essential tracing and monitoring to ensure optimal performance.

Most tracing and monitoring behaviors are controlled through the administrative console. Validate that the appropriate level of tracing and monitoring is set for the PMI monitoring, logging, and tracing settings through the administrative console.

Use the administrative console to validate that the **Audit logging** and **Common Event Infrastructure logging** check boxes are cleared in the Business Flow Manager and the Human Task Manager, unless these capabilities are required for business reasons.

For business processes, Integration Designer is also used to control event monitoring. Check the Event Monitor tab for your components and business processes to ensure that event monitoring is applied judiciously.

For BPMN business process definitions (BPDs), auto-tracking is enabled by default. If business requirements do not require tracking events for a BPD, turn off auto-tracking. If event tracking is required, consider creating a tracking group to define a small set of events for tracking purposes.

## 4.7.2 Tuning for large objects

This section describes tuning for performance when you use large objects (LOBs).

#### Increasing the Java heap size to its maximum

One of the key factors affecting large object processing is the maximum size of the Java heap. This section describes how to set the heap size as large as possible on two commonly used platforms, WIndows and AIX.

- ► Windows (32-bit)
  - Because of address space limitations in the Windows 32-bit operating system, the largest heap that can be obtained is 1.4 GB to 1.6 GB for 32-bit JVMs.
- ► AIX (32-bit)

On AIX 32-bit systems, the Java 5 and Java 6 JVM typically support heaps in the range of 2 GB to 2.4 GB. Because the 4 GB address space allowed by the 32-bit system is shared with other resources, the actual limit of the heap size depends on the memory that is used by these resources. These resources include thread stacks, JIT compiled code, loaded classes, shared libraries, and buffers used by OS system services. A large heap squeezes address space reserved for other resources and might cause runtime failures.

Setting maximum heap sizes applies only to 32-bit JVMs; when using 64-bit JVMs, the heap size is constrained only by the amount of available physical memory. The suggested configuration for Business Process Manager servers is 64-bit.

For comprehensive heap setting techniques, see 4.16, "Advanced Java heap tuning" on page 91.

#### Reducing or eliminating other processing while processing a LOB

One way to allow for larger object sizes is to limit concurrent processing within the JVM. Do not expect to process a steady stream of the largest objects possible concurrently with other Business Process Manager server and WebSphere Adapters activities. The operational assumption when considering large objects is that not all objects are large or very large and that large objects do not arrive often, perhaps only once or twice per day. If more than one very large object is being processed concurrently, the likelihood of failure increases dramatically.

The size and number of the normally arriving smaller objects affect the amount of Java heap memory consumption in the system. In general, the heavier the load on a system when a large object is being processed, the more likely that memory problems are encountered.

For adapters, the amount of concurrent processing can be influenced by setting the pollPeriod and pollQuantity parameters. To allow for larger object sizes, set a relatively high value for pollPeriod (for example, 10 seconds) and low value for pollQuantity (for example, 1 second) to minimize the amount of concurrent processing that occurs. These settings are not optimal for

peak throughput, so if an adapter instance must support both high throughput for smaller objects interspersed with occasional large objects, you must make trade-offs.

## 4.7.3 Tuning for maximum concurrency

For most high-volume deployments on server-class hardware, many operations present themselves to take place simultaneously. Tuning for maximum concurrency ensures that the server accepts enough load to saturate its core. One indication of an inadequately tuned configuration is when additional load does not result in additional core use while the cores are not fully used. To optimize these operations for maximum concurrency, the general guideline is to follow the execution flow and remove bottlenecks one at a time.

Higher concurrent processing means higher resource requirements (memory and number of threads) on the server. High concurrent processing must be balanced with other tuning objectives, such as the handling of large objects, handling large numbers of users, and providing good response time.

#### Tuning edging components for concurrency

The first step in tuning edging components for concurrency is to ensure that business objects are handled concurrently at the edge components of Business Process Manager solutions. If the input business objects come from the adapter, ensure that the adapter is tuned for concurrent delivery of input messages.

If the input business objects come from WebServices export binding or direct invocation from Java Server Pages (JSPs) or servlets, make sure the WebContainer thread pool is sized right. For example, to allow for 100 in-flight requests to be handled concurrently by a Business Process Manager server, the maximum size of the WebContainer thread pool must be set to 100 or larger.

If the input business objects come from messaging, you must tune the ActivationSpec (MDB bindings) and Listener ports (WebSphere MQ or MQJMS bindings).

#### Tuning message-driven bean ActivationSpec properties

For each JMS export component, there is an MDB and its corresponding ActivationSpec in the Java Naming and Directory Interface (JNDI name is module name/export component name\_AS). The default value for maxConcurrency of the JMS export MDB is 10, meaning up to 10 business objects from the JMS queue can be delivered to the MDB threads concurrently. Change it to 100 if a concurrency of 100 is wanted.

The Tivoli Performance Viewer can be used to monitor the maxConcurrency parameter. For each message being processed by an MDB, there is a message on the queue marked as being locked inside a transaction (which is removed after the onMessage completes). These messages are classed as unavailable. The PMI metric UnavailableMessageCount gives you the number of unavailable messages on each queue point. Check this value by selecting the resource name and then clicking SIB Service  $\rightarrow$  SIB Messaging Engines. Select the bus name and click Destinations  $\rightarrow$  Queues.

If any queue has maxConcurrency or more unavailable messages, this condition implies that the number of messages on the queue is currently running above the concurrency maximum of the MDB. If this situation occurs, increase the maxConcurrency setting for that MDB.

The maximum batch size in the activation specification also has an impact on performance. The default value is 1 (one). The maximum batch size value determines how many messages are taken from the messaging layer and delivered to the application layer in a single step. This batch size value does not mean that this work is done within a single transaction, and thus

this setting does not influence transactional scope. Increase this value (for example, to 8) for activation specs that are associated with SCA modules and long-running business processes to improve performance and scalability, especially for large multi-core systems.

#### Configuring thread pool sizes

The sizes of thread pools have a direct impact on the ability of a server to run applications concurrently. For maximum concurrency, you must set the thread pool sizes to optimal values. Increasing the maxConcurrency parameter or Maximum sessions parameter only enables the concurrent delivery of business objects from the JMS or WebSphere MQ queues. For a Business Process Manager server to process multiple requests concurrently, you must increase the corresponding thread pool sizes to allow higher concurrent execution of these MDB threads.

MDB work is dispatched to threads allocated from the default thread pool. All MDBs in the application server share this thread pool unless a different thread pool is specified. This condition means that the default thread pool size needs to be larger, probably significantly larger, than the maxConcurrency parameter of any individual MDB.

Threads in the WebContainer thread pool are used for handling incoming HTTP and web services requests. This thread pool is shared by all applications deployed on the server, and you must tune it, likely to a higher value than the default.

Object request broker (ORB) thread pool threads are employed for running ORB requests (for example, remote EJB calls). The thread pool size needs to be large enough to handle requests coming through the interface, such as certain human task manager APIs.

#### Configuring dedicated thread pools for message-driven beans

The default thread pool is shared by many WebSphere Application Server tasks. It is sometimes preferable to separate the execution of JMS MDBs to a dedicated thread pool. Complete the following steps to change the thread pool used for JMS MDB threads:

- Create a thread pool (for example, MDBThreadPool) on the server by clicking Servers →
   Server Types → WebSphere application servers → server → Thread pools. Then
   click New.
- 2. Open the service integration bus (SIB) JMS Resource Adapter administrative console with server scope by clicking Resources → Resource Adapters → Resource adapters. If the adapter is not visible, go to Preferences, and select the Show built-in resources check box.
- 3. Change the thread pool alias from **Default** to **MDBThreadPool**.
- 4. Repeat steps 2 and 3 for SIB JMS resource adapters at the node and cell scope.
- 5. Restart the server so that the changes become effective.

SCA Module MDBs for asynchronous SCA calls use a separate resource adapter, the Platform Messaging Component SPI Resource Adapter. Follow the same steps to change the thread pool to a different one if you want.

Even with a dedicated thread pool, all MDBs that are associated with the resource adapter still share a thread pool. However, they do not have to compete with other WebSphere Application Server tasks that also use the default thread pool.

#### Configuring JMS and JMS service queue connection factories

Multiple concurrently running threads might cause bottlenecks on resources such as JMS and database connection pools if such resources are not tuned properly. The Maximum Connections pool size parameter specifies the maximum number of physical connections that can be created in this pool. These physical connections interface with back-end

resources (for example, a DB2 database). After the thread pool limit is reached, the requester cannot create new physical connections and must wait until a physical connection that is currently in use is returned to the pool, or a ConnectionWaitTimeout exception is issued.

For example, if you set the Maximum Connections value to 5, and there are five physical connections in use, the pool manager waits for the amount of time that is specified in Connection Timeout for a physical connection to become free. The threads waiting for connections to the underlying resource are blocked until the connections are freed and allocated to them by the pool manager. If no connection is freed in the specified interval, a ConnectionWaitTimeout exception is issued.

If you set Maximum Connections property to 0 (zero), the connection pool is allowed to grow infinitely. This setting has the side effect of causing the Connection Timeout value to be ignored.

The general guideline for tuning connection factories is that their maximum connection pool size must match the number of concurrent threads multiplied by the number of simultaneous connections per thread.

For each JMS, WebSphere MQ, or MQJMS Import, a connection factory exists that was created during application deployment. Make the Maximum Connections property of the connection pool, associated with the JMS connection factory, large enough to provide connections for all threads concurrently running in the import component. For example, if 100 threads are expected to run in a given module, set the Maximum Connections property to 100. The default is 10.

From the connection factory configuration panel, click **Additional Properties** → **Connection pool properties**. Set the Maximum Connections property to the maximum size of the connection pool.

#### Configuring data source options

Make the Maximum Connections property of data sources large enough to allow concurrent access to the databases from all threads. Typically, a number of data sources are configured in Business Process Manager servers (for example, the BPEDB data source, the TWPROC data sources, the TWPERFDB data sources, the WPSDB data source, and the messaging engine database data sources). Set the Maximum Connections property of each data source to match the maximum concurrency of other system resources as described in 4.7.3, "Tuning for maximum concurrency" on page 64.

#### Setting data source prepared statement cache size

The BPC container uses prepared statements extensively. Set the statement cache sizes large enough to avoid repeatedly preparing statements for accessing the databases.

Set the prepared statement cache for the BPEDB to at least 300.

## 4.7.4 Messaging tuning

This section describes performance tuning for messaging.

#### Choosing data store or file store for messaging engines

Messaging engine persistence is backed by a database. However, a stand-alone Business Process Manager configuration might have the persistence storage of BPE and SCA buses backed by the file system (file store). You must choose a file store at profile-creation time. Use the Profile Management Tool to create a new stand-alone enterprise service bus profile or stand-alone process server profile:

- 1. Click Profile Creation Options  $\rightarrow$  Advanced profile creation  $\rightarrow$  Database Configuration.
- 2. Select the **Use a file store for Messaging Engine (MEs)** check box. When this profile is used, file stores are used for BPE and SCA service integration buses.

#### Setting data buffer sizes (discardable or cached)

The DiscardableDataBufferSize property is the size in bytes of the data buffer uses when processing best-effort non-persistent messages. The purpose of the discardable data buffer is to hold message data in memory because this data is never written to the data store for this quality of service. Messages that are too large to fit into this buffer are discarded.

The CachedDataBufferSize property is the size in bytes of the data buffer used when processing all messages other than best-effort non-persistent messages. The purpose of the cached data buffer is to optimize performance by caching in memory data that might otherwise need to be read from the data store.

You can set the DiscardableDataBufferSize and CachedDataBufferSize in the administrative console:

- 1. Click Service Integration-Buses and select the bus name.
- 2. Click **Messaging Engines** and select the messaging engine name.
- Click Additional properties → Custom properties and enter the values for DiscardableDataBufferSize and CachedDataBufferSize.

# Using a high-performance database management system for messaging engine data stores

For better performance, use production-quality databases, such as DB2, for the messaging engine data stores. You can choose the database at profile creation time using the advanced profile creation option.

#### Creating the DB2 database and loading the data store schema

Instead of having one DB2 database per messaging engine, we put all messaging engines into the same database, and using different schema to separate them, as shown in Table 4-1.

Table 4-1	Messaging	engine	schemas
-----------	-----------	--------	---------

Schema	Messaging engine
SCASYS	box01-server1.SCA.SYSTEM.box01Node01Cell.Bus
SCAAPP	box01-server1.SCA.APPLICATION. box01Node01Cell.Bus
CEIMSG	box01-server1.CommonEventInfrastructure_Bus
BPCMSG	box01-server1.BPC.box01Node01Cell.Bus

Use the following steps to place all messaging engines into the same database:

1. Create one schema definition for each messaging engine with the following command:

```
\label{local_was_install} WAS\ Install \verb|\bin\sibDDLGenerator.bat -system db2 -version 8.1 -platform windows -statementend; -schema BPCMSG -user user >createSIBSchema_BPCMSG.ddl
```

- In this syntax (used on a Windows operating system), WAS Install represents the Business Process Manager installation directory, and user represents the user name.
- Repeat the command for each schema or messaging engine.
- To distribute the database across several disks, edit the created schema definitions, and
  put each table in a table space, named after the schema used. For example, SCAAPP
  becomes SCANODE\_TS, CEIMSG becomes CEIMSG\_TS, and so on. After editing, the
  schema definition should look like Example 4-1.

#### Example 4-1 Schema definition

```
CREATE SCHEMA CEIMSG;
CREATE TABLE CEIMSG.SIBOWNER (
    ME_UUID VARCHAR(16),
    INC_UUID VARCHAR(16),
    VERSION INTEGER,
    MIGRATION_VERSION INTEGER
) IN CEIMSG_TB;
CREATE TABLE CEIMSG.SIBCLASSMAP (
    CLASSID INTEGER NOT NULL,
    URI VARCHAR(2048) NOT NULL,
    PRIMARY KEY(CLASSID)
) IN CEIMSG_TB;
....
```

Another possibility is to separate table spaces for the various tables. Optimal distribution depends on application structure and load characteristics. In this example, one table space per data store is used.

- 4. After creating all schema definitions and defined table spaces for the tables, create a database named SIB.
- 5. Create the table spaces and distribute the containers across available disks by issuing the following command for a system managed table space:

```
DB2 CREATE TABLESPACE CEIMSG_TB MANAGED BY SYSTEM USING( '<path>\CEIMSG_TB' ) Place the database log on a separate disk, if possible.
```

6. Create the schema of the database by loading the four schema definitions into the database.

For more information about database and DB2 tuning, see the following sections:

- ► 4.13, "General database tuning" on page 80
- 4.14, "DB2-specific database tuning" on page 82

#### Creating the data sources for the messaging engines

Create a data source for each messaging engine and configure each messaging engine to use the new data store using the administrative console:

- Create a JDBC provider of type DB2 Universal JDBC Driver Provider for the non-XA data sources if it does not exist. The XA DB2 JDBC Driver Provider should exist if BPC was configured correctly for DB2.
- 2. Create four new JDBC data sources, one for CEI as an XA data source, and the remaining three as single-phase commit (non-XA) data sources.

Table 4-2 provides new names for the data sources.

Table 4-2 New data sources

Name of data source	JNDI Name	Type of JDBC provider
CEIMSG_sib	jdbc/sib/CEIMSG	DB2 Universal (XA)
SCAAPP_sib	jdbc/sib/SCAAPPLICATION	DB2 Universal
SCASYSTEM_sib	jdbc/sib/SCASYSTEM	DB2 Universal
BPCMSG_sib	jdbc/sib/BPCMSG	DB2 Universal

When creating a data source, complete the following tasks.:

- 1. Clear the Use this Data Source in container managed persistence (CMP) check box.
- 2. Set a component-managed authentication alias.
- 3. Set the database name to the name used for the database created earlier for messaging (for example, Service Integration Bus).
- 4. Select a driver type of type 2 or type 4. DB2 should use the JDBC Universal Driver type 2 connectivity to access local databases, and type 4 connectivity to access remote databases. A type 4 driver requires a host name and valid port to be configured for the database.

#### Changing the data stores of the messaging engines

Use the administrative console to change the data stores of the messaging engines:

- 1. In the Navigation panel, click **Service Integration** → **Buses** and change the data stores for each bus and messaging engine that is displayed.
- 2. Put in the new JNDI and schema name for each data store. Clear the **Create Tables** check box because the tables are already created.
  - The server immediately restarts the messaging engine. The SystemOut.log file shows the results of the change and indicates whether the messaging engine starts successfully.
- 3. Restart the server and validate that all systems come up using the updated configuration.

The last remaining task is tuning the database. For more information about database and DB2-specific tuning, see the following sections:

- ► 4.13, "General database tuning" on page 80
- ► 4.14, "DB2-specific database tuning" on page 82

## 4.7.5 Clustered topology tuning

One reason for deploying a clustered topology is to add more resources to system components that are bottlenecked as a result of increasing load. Ideally, you can scale up a topology incrementally to match the required load. The Business Process Manager Network Deployment (ND) infrastructure provides this capability. However, effective scaling still requires standard performance monitoring and bottleneck analysis techniques.

The following list details several considerations and tuning guidelines for configuring a clustered topology. In the description, the assumption is that additional cluster members also imply additional server hardware.

- ► If deploying more than one cluster member (JVM) on a single physical system, monitoring the resource use (processor cores, disk, network, and other components) of the system as a whole is important. Also monitor the resources that are used by each cluster member. With monitoring, you can detect a system bottleneck because of a particular cluster member.
- ▶ If all App Target members of a cluster are bottlenecked, you can scale by adding one or more App Target members to the cluster, backed by appropriate physical hardware.
- ▶ If a single server or cluster member is the bottleneck, consider additional factors:
  - A messaging engine in a cluster with a "One of N" policy (to preserve event ordering)
    might become the bottleneck. The following scaling options are available to correct
    this issue:
    - Host the active cluster member on a more powerful hardware server or remove extraneous load from the existing server.
    - If the messaging engine cluster services multiple buses, and messaging traffic is spread across these buses, consider employing a separate messaging engine cluster per bus.
    - If a particular bus is a bottleneck, consider whether destinations on that bus can
      tolerate out-of-order events. In this case, the cluster policy can be changed to allow
      workload balancing with partitioned destinations. Partitioning a bus also includes
      considerations for balancing work across the messaging engine cluster members.
  - A database server might become the bottleneck. Consider the following approaches to correct this issue:
    - If the database server is hosting multiple databases that are active (for example, BPMDB, CMNDB, PDWDB, BPEDB), consider hosting each database on a separate server.
    - If a single database is driving load, consider a more powerful database server.
    - Beyond these items, you can use database partitioning and clustering capabilities.

## 4.7.6 Web services tuning

If the target of the web services import binding is hosted locally in the same application server, you can further improve the performance by taking advantage of the optimized communication path that is provided by the web container. Normally, requests from the web services clients are sent through the network connection between the client and the service provider. For local web services calls, however, WebSphere Application Server offers a direct communication channel, bypassing the network layer completely.

Complete the following steps to enable this optimization. Use the administrative console to change these values.

 Click Application servers and the then the name of the server that you want. Click Container Settings → Web Container Settings → Web container → Additional Properties → Custom Properties. Set the web container custom property enableInProcessConnections to true.

Do not use wildcard characters (\*) for the host name of the web container port. Replace it with the host name or IP address. The property can be accessed by clicking the following path:

Application servers  $\rightarrow$  messaging engine  $\rightarrow$  Container Settings  $\rightarrow$  Web Container Settings  $\rightarrow$  Web container  $\rightarrow$  Additional Properties  $\rightarrow$  Web container transport chains  $\rightarrow$  WCInboundDefault  $\rightarrow$  TCP inbound channel (TCP\_2)  $\rightarrow$  Related Items  $\rightarrow$  Ports  $\rightarrow$  WC\_defaulthost  $\rightarrow$  Host.

- 2. Use localhost instead of host name in the web services client binding. Using the actual host name (even if it is aliased to localhost), disables this optimization. To access the host name, use the following steps:
  - a. Click **Enterprise Applications** and select the application name.
  - b. Click Manage Modules and select the application EJB JAR file.
  - c. Click **Web services client bindings** → **Preferred port mappings** and select the binding name.

Use the localhost (for example, localhost: 9080) in the URL.

Make sure that there is not an entry for the server host name and IP address hosts file of your server for name resolution. An entry in the hosts file inhibits this optimization by adding name resolution processor usage.

# 4.7.7 Tuning Human Workflow for Business Space

The following optimizations are applicable when you use the Advanced Human Workflow Template with Business Space clients.

#### Optimizing performance when not using federation mode

If you are familiar with the performance characteristics of Human Workflow widgets with WebSphere Process Server V7.0, you might experience an initial performance degradation when using Human Workflow widgets such as Tasks, Processes, and Task Definitions in Business Process Manager V8.0. This degradation is apparent only if you use Business Space on a new (not a migrated) installation of Business Process Manager V8.0. These performance considerations apply if you use the Human Task Management widgets with only Business Process Definition (BPD) processes and human services on a single application server, or on a cluster.

This performance degradation is caused by the addition of a federation service layer and the higher number of items to be retrieved. Addition of the federated service layer is a usability enhancement initially delivered in Business Process Manager V7.5 that enables the display of all tasks in a single unified task list.

To check the Business Space target services configuration in the administration console, complete the following steps.

- 1. Open the IBM Business Process Manager Integrated Solutions Console.
- Click the Servers tab in the navigation bar.
- 3. Click WebSphere.
- 4. Click **Application Servers** server type and choose the application server on which you want to run Business Space.
- 5. In the Business Integration section on the Configuration tab, click the **Business Space Configuration** entry.
- 6. On the Business Space Configuration page, in the Additional Properties section, click the **REST service endpoint registration** entry.
- 7. On the REST service endpoint registration page, check the Service Endpoint Target values for the Process services and Task services REST endpoint types. The default initial setting is Federated REST services.

To improve performance by using the BPC REST End Point instead of the Federated REST Endpoint, complete the following steps:

- 1. Change the Business Space target services configuration in the administration console.
- 2. Change the Process services to the Business Process Choreographer REST services endpoint of the application server that is running your processes and human tasks.
- 3. Change the Tasks services to the Business Process Choreographer REST services endpoint of the application server that is running your processes and human tasks.
- 4. Click **OK** to save the configuration changes.
- 5. Log out of Business Space and then log in again.

## 4.7.8 Power management tuning

Power management is common in modern processor technology. Both Intel and POWER core processors have this capability. This capability delivers obvious benefits, but it can also decrease system performance when a system is under high load, so consider whether to enable power management. For example, with IBM POWER6® hardware, ensure that Power Saver Mode is not enabled unless that is what you want. One way to modify or check this setting on AIX is through the Power Management window on the Hardware Management Console (HMC).

# 4.7.9 Setting AIX threading parameters

The IBM JVM threading and synchronization components are based on threads implementation that are compliant with AIX POSIX. The following environment variable settings improve Java performance in many situations. The variables control the mapping of Java threads to AIX native threads, turn off mapping information, and allow for spinning on mutually exclusive (mutex) locks:

- ► export AIXTHREAD COND DEBUG=OFF
- export AIXTHREAD MUTEX DEBUG=OFF
- ► export AIXTHREAD RWLOCK DEBUG=OFF
- export AIXTHREAD SCOPE=S
- ► export SPINLOOPTIME=2000

# 4.8 Tuning for Business Process Execution Language business processes

This section provides advanced tuning tips for Business Process Execution Language (BPEL) business processes.

## 4.8.1 Tuning Work Manager-based navigation for business processes

Work Manager-based navigation is the default navigation mode for BPEL business processes (rather JMS-based navigation). Work Manager-based navigation provides two methods to optimize performance, keeping the quality of service of (JMS-based) process navigation consistent with persistent messaging:

Work Manager-based navigation

WorkManager is a thread pool of Java Platform Enterprise Edition threads. WorkManager process navigation takes advantage of an underlying capability of WebSphere Application Server to start the processing of ready-to-navigate business flow activities without using messaging as provided by JMS providers.

InterTransactionCache

This cache is a part of the Work Manager-based navigation mode that holds process instance state information in memory, reducing the need to retrieve information from the BPE database.

Several parameters control usage of these two optimizations. In the administrative console, to find the first set of these parameters, use the following steps:

- 1. Click **Application Servers** and select the server name you want.
- 2. Click Business Integration  $\rightarrow$  Business Process Choreographer  $\rightarrow$  Business Flow Manager  $\rightarrow$  Business Process Navigation Performance.

Enabling this capability at the cluster level overrides the settings for a specific server. So, in a clustered environment, enabling this capability at the cluster lever is the easiest approach.

Key parameters are as follows:

► Enable advanced performance optimization

Select this property to enable both the Work Manager-based navigation and InterTransactionCache optimizations.

Work-Manager-Based Navigation Message Pool Size

This property specifies the size of the cache used for navigation messages that cannot be processed immediately, provided Work Manager-based navigation is enabled. The cache defaults to the message size (computed by 10 times the thread pool size of the BPENavigationWorkManager). If this cache reaches its limit, JMS-based navigation is used for new messages. For optimal performance, ensure that this Message Pool size is set to a sufficiently high value.

▶ InterTransaction Cache Size

This property specifies the size of the cache used to store process state information that has also been written to the BPE database. Set this value to twice the number of parallel running process instances. The default value for this property is the thread pool size of the BPENavigationWorkManager.

In addition, you can customize the number of threads for the Work Manager that use these settings by clicking Resources  $\rightarrow$  Asynchronous Beans  $\rightarrow$  Work Managers  $\rightarrow$  BPENavigationWorkManager.

Increase the minimum number of threads from its default value of 5, and increase the maximum number of threads from its default value of 12, using the methodology outlined in 4.7.3, "Tuning for maximum concurrency" on page 64. If the thread pool size is modified, also modify the work request queue size and set it to be twice the maximum number of threads.

# 4.8.2 Tuning the business process container for Java Message Service navigation

If JMS-based navigation is configured, you must optimize the following resources for efficient navigation of business processes:

► Activation specification BPEInternalActivationSpec

The Maximum Concurrent Endpoints parameter specifies the parallelism that is used for process navigation across all process instances. Increase the value of this parameter to increase the number of business processes run concurrently. Find this resource in the administrative console by clicking **Resources**  $\rightarrow$  **Activation Specifications**  $\rightarrow$  **BPEInternalActivationSpec**.

► JMS connection factory BPECFC

Set the connection pool size to the number of threads in the BPEInternalActivationSpec plus 10%. Find this resource in the administrative console by clicking **Resources**  $\rightarrow$  **JMS**  $\rightarrow$  **Connection factories**  $\rightarrow$  **BPECFC**  $\rightarrow$  **Connection pool properties**. This connection factory is also used when Work Manager-based navigation is in use, but only for error situations or if the server is highly overloaded.

# 4.8.3 Tuning task list and process list queries

The programmer creates task list and process list queries in Business Process Manager applications by using the standard query APIs, that is, query() and queryAII(), and related REST and web services interfaces. Task list and process list queries are also created by the query table APIs queryEntities() and queryRows(). All task list and process list queries result in SQL queries against the BPC database. These SQL queries might need special tuning to provide optimal response times, as follows:

- ▶ Up-to-date database statistics are key for good SQL query response times.
- ► Databases offer tools to tune SQL queries. In most cases, additional indexes improve query performance with some potential impact on process navigation performance. For DB2, the DB2 design advisor can be used to guide in choosing indexes.

# 4.8.4 Tuning Business Process Choreographer API calls

Business Process Choreographer (BPC) API calls are triggered by requests external to the Business Process Manager server run time. Examples include remote EJB requests, web service requests, web requests over HTTP, requests that come through the SCA layer, or JMS requests. The connection pools associated with each of these communication mechanisms might need tuning.

Consider the following hints when tuning the connection pools:

- ► API calls for task list and process list queries might take more time to respond, depending on the tuning of the database and the amount of data in the database.
- ► Ensure that concurrency (parallelism) is sufficiently high to handle the load and to use the processor. However, increasing the parallelism of API call execution beyond what is necessary can negatively influence response times. Also, increased parallelism can put excessive load on the BPC database. When tuning the parallelism of API calls, measure response times before and after tuning, and adjust the parallelism if necessary.

## 4.8.5 Tuning intermediate components for concurrency

If the input business object is handled by a single thread from end to end, the tuning for the edge components is normally adequate. In many situations, however, multiple thread switches exist during the end-to-end execution path. Tuning the system to ensure adequate concurrency for each asynchronous segment of the execution path is important.

Asynchronous invocations of an SCA component use an MDB to listen for incoming events that arrive in the associated input queue. Each SCA module defines an MDB and its corresponding activation specification (JNDI name is sca/module name/ActivationSpec). The SCA module MDB is shared by all asynchronous SCA components within the module, including SCA export components. Take this shared state into account when you configure the maxConcurrency property value of ActivationSpec. SCA module MDBs use the same default thread pool as those for JMS exports.

The asynchronicity in a long-running business process occurs at transaction boundaries (see 3.2.9, "Transactional considerations" on page 38 for more details about settings that affect transaction boundaries). BPE defines an internal MDB and its ActivationSpec as BPEInternalActivationSpec. The maxConcurrency parameter must be tuned by following the same guideline as for SCA module and JMS export MDBs (as described in 4.7.3, "Tuning for maximum concurrency" on page 64).

The only issue is that only one BPEInternalActivationSpec exists for a single Business Process Manager server.

# 4.9 Mediation flow component tuning

Additional configuration options are relevant to tuning Mediation Flow Components. These are described in this section.

See 5.2, "Mediation Flow Component settings" on page 104 for a suggested set of initial values to use.

# 4.9.1 Tuning the database if using persistent messaging

If you use persistent messaging, the configuration of your database is important. Use a remote DB2 instance with a fast disk array as the database server. You might benefit from tuning the connection pooling and statement cache of the data source.

For more information about tuning DB2, see the following sections:

- ▶ 4.13, "General database tuning" on page 80
- ► 4.14, "DB2-specific database tuning" on page 82

See the relevant references in "Related publications" on page 107.

## 4.9.2 Disabling event distribution for Common Event Infrastructure

The event server that manages events can be configured to distribute events and log them to the event database. Some mediations only require events to be logged to a database. For these cases, performance improves by disabling event distribution. Because the event server might be used by other applications, it is important to check that none of them use event monitoring, which requires event distribution before disabling event distribution.

Event distribution can be disabled from the administrative console by clicking Service integration  $\rightarrow$  Common Event Infrastructure  $\rightarrow$  Event service  $\rightarrow$  Event services  $\rightarrow$  Default Common Event Infrastructure event server. Clear the Enable event distribution check box.

## 4.9.3 Configuring WebSphere Service Registry and Repository cache timeout

WebSphere Service Registry and Repository (WSRR) is used by WebSphere ESB for endpoint lookup. When accessing the WSRR (for example, using the endpoint lookup mediation primitive), results from the registry are cached in WebSphere ESB. You can configure the lifetime of the cached entries from the administrative console by clicking **Service Integration**  $\rightarrow$  **WSRR Definitions** and entering the WSRR definition name. Then click **Timeout of Cache** and set a value for the cached registry results.

Validate that the timeout is a sufficiently large value. The default timeout is 300 seconds, which is reasonable from a performance perspective. A value that is too low results in frequent lookups to the WSRR, which can be expensive (especially if retrieving a list of results) and includes the associated network latency if the registry is on a remote machine.

# 4.10 Business Monitor tuning

This section provides advanced tuning suggestions for Business Monitor.

# 4.10.1 Configuring Java heap sizes

The default maximum heap size in most implementations of Java is too small for many of the servers in this configuration. The Business Monitor Launchpad installs the Business Monitor and its prerequisite servers with larger heap sizes, but you might check that these sizes are appropriate for your hardware and workload.

# 4.10.2 Configuring Common Event Infrastructure

By default, when an event arrives at CEI, it is delivered to the registered consumer (in this case, a particular monitor model) and into an additional default queue. Performance improves by avoiding this double-store by removing the All Events event group:

- In the administrative console, click Service Integration → Common Event Infrastructure → Event Service → Event Services → Default Common Event Infrastructure event server → Event Groups
- 2. Remove the event group.

Beyond its persistent delivery of events to registered consumers, CEI offers the ability to explicitly store events in a database. Database event storage requires significant processor usage, so avoid storing the events in the database if this additional functionality is not needed. You can also configure the CEI data store:

- In the administrative console, select Service Integration → Common Event Infrastructure → Event Service → Event Services → Default Common Event Infrastructure event server.
- 2. Clear the **Enable Data Store** check box.

## 4.10.3 Configuring message consumption batch size

Processing events in large batches is much more efficient than doing it one at a time. Up to some limit, the larger the batch size, the higher the throughput rate. But there is a trade-off: processing and persisting events to the Monitor database is done as a transaction. Although a larger batch size yields better throughput, it costs more if you must roll back. If you experience frequent rollbacks, consider reducing the batch size. You can reduce cache size in the administrative console under the server scope:

- 1. Click **Applications** → **Monitor Models** and select the version of the batch.
- 2. Click Runtime Configuration → Tuning → Message Consumption Batch size and set the batch size you want. The default value is 100.

## 4.10.4 Enabling key performance indicator caching

The cost of calculating aggregate key performance indicator (KPI) values increases as completed process instances accumulate in the database. A KPI cache is available to reduce the resource usage of these calculations at the cost of some staleness in the results. The refresh interval is configurable in the WebSphere administrative console:

- 1. Click **Applications** → **Monitor Models** and select the version.
- 2. Click Runtime Configuration → KPI → KPI Cache Refresh Interval.

A value of zero (the default) disables the cache.

## 4.10.5 Using table-based event delivery

There are two ways in which events can be delivered by CEI to a monitor model:

- ► Through a JMS queue
- Through a database table

You can choose a method at application installation time for a monitor model. A suggestion is to choose table-based event delivery (sometimes called *queue bypass*), both for reliability and for performance and scalability reasons.

# 4.10.6 Enabling the Data Movement Service

By default, the same tables are used for event processing and for dashboard reporting. You can enable an optional scheduled service, called the *Data Movement Service (DMS)* to switch dashboard reporting against a separate set of tables. DMS also periodically copies the data from the event processing tables for the server to the dashboard reporting tables.

This processing and reporting mode optimizes the following components:

- ► Indexes for each table
- ► Event processing tables for the server for quick insert/update/delete
- Dashboard reporting tables for common dashboard-related queries

We suggest that you enable DMS in any production scenario.

# 4.11 Enable browser caching

Business Process Manager clients rely heavily on AJAX and JavaScript code; their performance depends on the browser's efficiency in processing this code. To improve Business Process Manager client-response times you might need to adjust both HTTP server and client browser settings. This section covers ensuring that browser caching is enabled. HTTP server caching is addressed in 4.12, "Tuning the HTTP server" on page 79.

## 4.11.1 Ensuring browser cache is enabled in Internet Explorer

By default, Business Process Manager allows the browser to cache static information such as style sheets and JavaScript files for 24 hours. However, if the browser is configured in a way that does not cache data, the same resources are loaded repeatedly, resulting in long page-load times.

To enable caching, use the following steps:

- 1. Click Tools  $\rightarrow$  Internet Options  $\rightarrow$  General  $\rightarrow$  Browsing History.
- 2. Set the cache size, indicated by **Disk space to use**, to at least 50 MB.

#### Ensure browser cache is not cleared on logout

Modern browsers have options to clear the cache on exit; make sure that this setting is not enabled.

Use the following procedure to disable cache clearing:

- 1. Click **Tools** → **Internet Options**.
- Under the General tab, make sure the Delete browser history on exit check box is cleared.
- 3. Click the **Advanced** tab and make sure the **Empty Temporary Internet Files folder** when browser is closed check box is cleared. Click **OK** to save the settings.
- 4. Restart your browser to make sure that the changes have taken effect.

## 4.11.2 Ensuring browser cache is enabled in Firefox

By default, Business Process Manager allows the browser to cache static information such as style sheets and JavaScript files for 24 hours. However, if the browser is configured in a way that does not cache data, the same resources are loaded repeatedly, resulting in long page-load times.

To enable caching, use the following steps:

- 1. Click Tools  $\rightarrow$  Options  $\rightarrow$  Advanced  $\rightarrow$  Network  $\rightarrow$  Offline Storage.
- Set the offline storage to at least 50 MB.

Use the following procedure to enable cache clearing:

- 1. Click **Tools** → **Options**.
- 2. Click the **Privacy** tab and make sure that it reads Firefox will: Remember History. Click **OK**. This setting enables caching.

If you click **Never remember history**, caching is disabled and you must change the setting.

If you click **Use custom settings for history**, you have additional options that still allow caching:

- If you select Automatically start Firefox in a private browsing session, caching is enabled. However, after the browser is closed, everything is erased (not only cache, but also browsing history) as though you were never using the browser.
- If private browsing is not selected, make sure the Clear history when Firefox closes check box is cleared.
- 3. Restart the browser to apply the changes.

# 4.12 Tuning the HTTP server

The Process Server and Process Center in production scenarios are generally deployed by using a topology that includes an HTTP server or an HTTP server plug-in. The Process Portal and Process Designer send multiple requests to their respective server, which are then handled by this HTTP server. To minimize the number of requests and the size of the response data to obtain good user response times, tune your HTTP server to efficiently handle the expected load.

In particular, ensure that caching is effectively enabled in the HTTP server. Much of the content that is requested by the Process Portal and Process Designer is static (for example images and JavaScript files), and can be cached in the browser. Of course, ensure that browser caching is enabled first, but also tune the HTTP server to support caching at that level. Specifically in the httpd.conf file, use the following caching and compression settings:

- ▶ nExpiresActive on
- ► ExpiresByType image/gif A86400
- ExpiresByType image/jpeg A86400
- ► ExpiresByType image/bmp A86400
- ExpiresByType image/png A86400
- ► ExpiresByType application/x-javascript A86400
- ► ExpiresByType text/css A86400

**Tip:** 86400 seconds = 1 day

For more information about tuning the IBM HTTP Server, which is included as part of Business Process Manager V8.0, see the IBM HTTP Server Performance Tuning page:

http://publib.boulder.ibm.com/httpserv/ihsdiag/ihs performance.html

For more information about tuning Business Space, see *Scalability and Performance of Business Space and Human Task Management Widgets in WebSphere Process Server v7* white paper:

http://www.ibm.com/support/docview.wss?uid=swg27020684&wv=1

# 4.13 General database tuning

This section provides general tuning hints for databases.

## 4.13.1 Providing adequate statistics for optimization

Databases usually offer a wide variety of available choices when determining the best approach to access data. Statistics, which describe the shape of the data, are used to guide the selection of a low-cost data access strategy. Statistics are maintained in tables and indexes. Examples of statistics include the number of rows in a table and the number of distinct values in a certain column.

Gathering statistics can be expensive, but fortunately, for many workloads, a set of representative statistics allows for good performance over a large span of time. Refreshing statistics periodically if the data population shifts dramatically might be necessary.

## 4.13.2 Placing database log files on a fast disk subsystem

Databases are designed for high availability, transactional processing, and recoverability. For performance reasons, changes made to table data might not be written immediately to disk. These changes can be recovered if they are written to the database log. Updates are made to database log files when the log buffer fills, at transaction-commit time, and for some implementations after a maximum interval of time.

As a result, database log files might be heavily used. More important, the log-writes hold commit operations pending, meaning that the application is synchronously waiting for the write to complete. Therefore, the performance of write access to the database log files is critical to overall system performance. For this reason, we suggest that database log files be placed on a fast disk subsystem with write-back cache.

# 4.13.3 Placing logs on a separate device from the table space containers

A basic strategy for all database storage configurations is to place the database logs on dedicated physical disks, ideally on a dedicated disk adapter. This placement reduces disk access contention between I/O to the table space containers and I/O to the database logs and preserves the mostly sequential access pattern of the log stream. Such separation also improves recoverability when log archival is employed.

# 4.13.4 Providing sufficient physical memory

Accessing data in memory is much faster than reading it from disk. Because 64-bit hardware is readily available and memory prices continue to fall, the sensible approach is to provision enough memory to avoid most disk reads in steady state for many performance-critical workloads.

Be careful to avoid virtual memory paging in the database machine. The database manages its memory with the assumption that it is never paged and does not cooperate well if the operating system swaps some of its pages to disk.

## 4.13.5 Avoiding double buffering

Because the database attempts to keep frequently accessed data in memory, in most cases, using file system caching offers no benefit. However, performance typically improves by using direct I/O, when files read by the database bypass the file system cache and only one copy of the data is held in memory. By using direct I/O, the system can allocate more memory to the database and avoid resource usage in the file system as it manages its cache.

A further advantage can be gained on some operating systems, such as AIX, by using concurrent I/O. Using concurrent I/O bypasses per-file locking, shifting responsibility for concurrency control to the database and, in some cases, offering the possibility of more useful work to the adapter or the device.

An important exception to this guideline occurs for large objects (LOB, BLOB, CLOB, and others) that are not buffered by the database itself. In this case, a possible advantage is to arrange for file system caching, preferably only for files that back large objects.

## 4.13.6 Refining table indexes as required

Business Process Manager products typically provide a reasonable set of indexes for the database tables they use. In general, creating indexes involves a tradeoff between the cost of queries and the cost of statements which insert, update, or delete data. For query-intensive workloads, providing a rich variety of indexes as required to allow rapid access to data makes sense. For update-intensive workloads, a helpful approach is to minimize the number of indexes defined, because each row modification might require changes to multiple indexes. Indexes are kept current even when they are infrequently used.

Index design therefore involves compromises. The default set of indexes might not be optimal for the database traffic generated by a Business Process Manager product in a specific situation. If database processor or disk use is high or there are concerns with database response time, it might be helpful to consider changes to the indexes.

DB2 and Oracle databases provide assistance in this area by analyzing indexes in the context of a given workload. These databases offer suggestions to add, modify, or remove indexes. One caveat is that if the workload does not capture all relevant database activity, a necessary index might appear unused, leading to a suggestion that it be dropped. If the index is not present, future database activity can suffer as a result.

# 4.13.7 Archiving completed process instances

Over time, completed process instances accumulate in the database of the servers. This accumulation can alter the performance characteristics of the solution being measured. It is helpful to archive completed process instances to ensure that the database size is controlled. If you do not archive completed process instances and Performance Data Warehouse events, they grow unbounded over time, which impacts overall system performance.

One symptom of this problem is long query times on Business Process Definition (BPD) and TASK tables. Another symptom is that your process server database tables occupy too much disk space. Both of these symptoms occur because completed BPD instances are not deleted from the system automatically. After a BPD instance is completed, the instance is typically no longer needed and therefore can be removed from the Process Server database. Business Process Manager provides a stored procedure, LSW\_BPD\_INSTANCE\_DELETE, which you can use to delete old instances. Archiving procedures are in the following technote:

http://www.ibm.com/support/docview.wss?uid=swg21439859

# 4.14 DB2-specific database tuning

Providing a comprehensive DB2 tuning guide is beyond the scope of this paper. However, a few general guidelines can assist in improving the performance of DB2 environments. This section describes these rules and provides pointers to more detailed information.

The complete set of current DB2 manuals (including database tuning guidelines) is in the DB2 solution Information Center:

http://publib.boulder.ibm.com/infocenter/db2luw/v9r7/index.jsp

Another reference is the "Best practices for DB2 for Linux, UNIX, and Windows" page:

http://www.ibm.com/developerworks/data/bestpractices/db2luw/

## 4.14.1 Updating database statistics

DB2 provides an Automatic Table Maintenance feature that runs the RUNSTATS command in the background as required. Using RUNSTATS ensures that the correct statistics are collected and maintained. This feature is controlled with the auto\_runstats database configuration parameter and is enabled by default for databases created by DB2 9.1 and later. See the Configure Automatic Maintenance wizard at the database level in the DB2 Control Center.

One approach to updating statistics manually on all tables in the database is to use the REORGCHK command. Dynamic SQL, such as that produced by Java Database Connectivity (JDBC), immediately takes the new statistics into account. Static SQL, such as that in stored procedures, must be explicitly rebound in the context of the new statistics. Example 4-2 shows DB2 commands that perform the steps to gather basic statistics on database DBNAME.

#### Example 4-2 Gathering basic statistics on database DBNAME

```
db2 connect to DBNAME
db2 reorgchk update statistics on table all
db2 connect reset
db2rbind DBNAME all
```

Run REORGCHK and **rebind**, when the system is relatively idle, to ensure that a stable sample might be acquired and to avoid possible deadlocks in the catalog tables.

Gathering additional statistics is a better approach; therefore, consider also using the following command for every table that requires attention:

runstats on table <schema>. with distribution and detailed indexes

## 4.14.2 Setting buffer pool sizes correctly

A *buffer pool* is an area of memory into which database pages are read, modified, and held during processing. Buffer pools improve database performance. If a required page of data is already in the buffer pool, that page is accessed faster than if the page must be read directly from disk. As a result, the size of the DB2 buffer pools is critical to performance.

The amount of memory used by a buffer pool depends on two factors:

- Size of buffer pool pages
- Number of pages allocated

Buffer pool page size is fixed at creation time and might be set to 4, 8, 16, or 32 KB. The most commonly used buffer pool is IBMDEFAULTBP, which has a 4000 MB page size.

All buffer pools are in database global memory, which is allocated on the database machine. The buffer pools must coexist with other data structures and applications, all without exhausting available memory. In general, having larger buffer pools improves performance up to a point by reducing I/O activity. Beyond that point, allocating additional memory no longer improves performance.

DB2 9.1 and later provide self-tuning memory management, which includes managing buffer pool sizes. The self\_tuning\_mem database level parameter, which is on by default, globally controls memory management. You can enable self-tuning for individual buffer pools by using SIZE AUTOMATIC at CREATE or ALTER time.

To choose appropriate buffer pool size settings manually, monitor database container I/O activity by using system tools or by using DB2 buffer pool snapshots. Be careful to avoid configuring large buffer pool size settings that lead to paging activity on the system.

## 4.14.3 Maintaining correct table indexing

The DB2 Design Advisor provides suggestions for schema changes, including changes to indexes. To open the Design Advisor, complete the following steps:

- 1. From the Control Center, right-click a database in the left column.
- 2. Click **DB2 Design Advisor** on the resulting menu.

## 4.14.4 Sizing log files appropriately

When using circular logging, it is important that the available log space permits dirty pages in the buffer pool to be cleaned at a reasonably low rate of speed. Changes to the database are immediately written to the log, but a well-tuned database coalesces multiple changes to a page before eventually writing that modified page back to disk. Naturally, changes recorded only in the log cannot be overwritten by circular logging. DB2 detects this condition and forces the immediate cleaning of dirty pages required to allow switching to a new log file. Although this mechanism protects the changes recorded in the log, it suspends all application logging until the necessary pages are cleaned.

DB2 works to avoid pauses when switching log files by proactively triggering page cleaning under control of the database level softmax parameter. The default value of 100 for softmax begins background cleaning when the size gap between the current head of the log and the oldest log entry recording a change to a dirty page exceeds 100% of one log file. In extreme cases, this asynchronous page cleaning cannot keep up with log activity, leading to log switch pauses that degrade performance.

Increasing the available log space gives asynchronous page cleaning more time to write dirty buffer pool pages and avoid log-switch pauses. A longer interval between cleanings offers the possibility for multiple changes to be coalesced on a page before it is written, which reduces the required write-throughput by making page cleaning more efficient.

Available log space is governed by the product of log file size and the number of primary log files, which are configured at the database level. The logfilsiz setting is the number of 4 KB pages in each log file. The logprimary setting controls the number of primary log files. The Control Center also provides a Configure Database Logging wizard.

As a starting point, try using 10 primary log files that are large enough so they do not wrap for at least a minute in normal operation.

Increasing the primary log file size has implications for database recovery. Assuming a constant value for softmax, larger log files mean that recovery might take more time. Although you can lower the softmax parameter to counter this effect, consider that more aggressive page cleaning might also be less efficient. Increasing the softmax parameter offers additional opportunities for write coalescing at the cost of longer recovery time.

The default value of softmax is 100, meaning that the database manager attempts to clean pages such that a single log file needs to be processed during recovery. For best performance, we suggest increasing this value to 300 as follows, meaning that three log files might need processing during recovery:

db2 update db config for <yourDatabaseName> using softmax 300

## 4.14.5 Using System Managed Storage for table spaces that contains LOBs

When creating REGULAR or LARGE table spaces in DB2 9.5 and later that contain performance critical LOB data, we suggest specifying MANAGED BY SYSTEM to gain the advantages of cached LOB handling in system managed storage (SMS).

This consideration applies to the following Business Process Manager-related products:

- ► Business Process Choreographer database (BPEDB)
- ► BPMN databases (twproc and twperfdb)
- ► Databases backing service integration bus messaging engine data stores

For background on using SMS for table spaces with large objects, see 4.13.5, "Avoiding double buffering" on page 81. A detailed explanation follows here.

DB2 table spaces can be configured with NO FILE SYSTEM CACHING, which in many cases improves system performance. If a table space is specified as MANAGED BY SYSTEM, then it uses SMS, which provides desirable special case handling for LOB data regarding caching. Even if NO FILE SYSTEM CACHING is in effect (by default or as specified), access to LOB data still uses the file system cache.

If a table space is MANAGED BY DATABASE, it uses Database Managed Storage (DMS), which does not differentiate between LOB and non-LOB data regarding caching. In particular, NO FILE SYSTEM CACHING means that LOB access reads and writes directly to disk. Unconditionally reading LOBs from disk can cause high disk use and poor database performance.

Since Version 9.1, DB2 has created, by default, databases that use automatic storage (AUTOMATIC STORAGE YES). Creating databases by using automatic storage means that the database that manages disk space allocates itself from one or more pools of available file system space called storage paths. If automatic storage is enabled, CREATE TABLESPACE uses it by default (MANAGED BY AUTOMATIC STORAGE). For non-temporary table spaces, REGULAR and LARGE, automatic storage is implemented using DMS on files.

Before DB2 9.5, the default caching strategy for table spaces was FILE SYSTEM CACHING. In version 9.5, this strategy was changed to NO FILE SYSTEM CACHING for platforms where direct I/O or concurrent I/O is available. Taking defaults on version 9.5, we now have a database with AUTOMATIC STORAGE YES, and a table space that is MANAGED BY AUTOMATIC STORAGE, and in many cases, NO FILE SYSTEM CACHING. Such a table space, which is implemented using DMS, does not cache LOBs in the buffer pool or the file system.

## 4.14.6 Ensuring sufficient locking resources are available

Locks are allocated from a common pool controlled by the locklist database level parameter, which is the number of 4000 pages set aside for this use. A second database level parameter, maxlocks, bounds the percentage of the lock pool held by a single application. When an application attempts to allocate a lock that exceeds the fraction allowed by maxlocks, or when the free lock pool is exhausted, DB2 performs lock escalation to replenish the supply of available locks. Lock escalation involves replacing many row locks with a single table-level lock.

Although lock escalation addresses the immediate problem of lock-pool overuse or starvation, it can lead to database deadlocks and therefore should not occur frequently during normal operation. In some cases, application behavior can be altered to reduce pressure on the lock pool by breaking up large transactions that lock many rows into smaller transactions. It is simpler to try tuning the database first.

Beginning with version 9, DB2 adjusts the locklist and maxlocks parameters automatically, by default. To tune these parameters manually, observe whether lock escalations are occurring either by examining the db2diag.log file or by using the system monitor to gather snapshots at the database level. If the initial symptom is database deadlocks, consider whether these deadlocks are initiated by lock escalations, as follows:

- Check the lock escalations count in the output.:
   db2 get snapshot for database <yourDatabaseName>
- 2. Obtain current values for locklist and maxlocks by examining the output.: db2 get db config for <yourDatabaseName>
- 3. If necessary, alter these values, for example, to 100 for locklist and 20 for maxlocks, as shown in Example 4-3.

Example 4-3 Setting values for locklist and maxlocks

db2 update db config for <yourDatabaseName> using locklist 100 maxlocks 20

When increasing the locklist size, consider the impacts of the additional memory allocation that is required. Often, the locklist is relatively small compared with memory dedicated to buffer pools, but the total memory required must not lead to virtual memory paging.

When increasing the maxlocks fraction, consider whether a larger value allows a few applications to drain the free lock pool. This drain might lead to a new cause of escalations as other applications needing relatively few locks encounter a depleted free lock pool. Often, a better way is to start by increasing locklist size alone.

# 4.14.7 Setting boundaries on the size of the catalog cache for clustered applications

The catalog cache is used to avoid repeating expensive activities, notably preparing execution plans for dynamic SQL. Therefore, an important consideration is to be sure that the cache is sized appropriately.

By default, several 4 KB pages of memory are allocated for each possible application as defined by the MAXAPPLS database parameter. The multiplier is 4 for DB2 9, and 5 for DB2 9.5 and later. MAXAPPLS is AUTOMATIC, by default, and its value are adjusted to match the peak number of applications connected at run time.

When running clustered applications, such as those deployed in the Business Process Choreographer in Business Process Manager V8.0, a value of more than 1000 for MAXAPPLS is possible. Such a value means that at least 4000 pages are allocated for the catalog cache, given default tuning. For the same workload, 500 pages are sufficient:

db2 update db config for <yourDatabaseName> using catalogcache sz 500

The default behavior assumes heterogeneous use of database connections. A clustered application typically receives more homogeneous use across connections, allowing a smaller package cache to be effective. Bounding the package cache size frees memory for other more valuable uses.

To tune the catalogcache\_sz database parameter manually, see the suggestions at the following website:

http://publib.boulder.ibm.com/infocenter/db2luw/v9/topic/com.ibm.db2.udb.admin.doc/doc/r0000338.htm

## 4.14.8 Sizing the database heap appropriately before DB2 9.5

DB2 9.5 and later provides the value of AUTOMATIC tuning of the database heap by default. We suggest using this value when available.

To tune the dbheap database parameter manually, see the suggestions documented at the following website:

http://publib.boulder.ibm.com/infocenter/db2luw/v9/topic/com.ibm.db2.udb.admin.doc/doc/r0000276.htm

## 4.14.9 Sizing the log buffer appropriately before DB2 9.7

Before DB2 Version 9.7, the default LOGBUFSZ was only eight pages. We suggest setting this value to 256, which is the default in Version 9.7:

db2 update db config for <yourDatabaseName> using logbufsz 256

# 4.14.10 Tuning for BPEL business processes

The following website explains the specification of initial DB2 database settings and provides examples of creating SMS table spaces for the BPEDB. It also contains useful links for planning and fine-tuning the BPEDB:

http://publib.boulder.ibm.com/infocenter/dmndhelp/v7r0mx/index.jsp?topic=/com.ibm.websphere.bpc.doc/doc/bpc/t5tuneint\_spec\_init\_db\_settings.html

The following website explains how to create DB2 databases for Linux, UNIX, and Windows for BPEL business processes. The website gives details about BPEDB creation, including pointers for creating scripts for a production environment:

http://publib.boulder.ibm.com/infocenter/dmndhelp/v7r0mx/index.jsp?topic=/com.ibm.
websphere.bpc.doc/doc/bpc/t2codbdb.html

## 4.14.11 Suggestions for Business Monitor

This section describes ways to tune and maximize the performance of Business Monitor V8.0.

#### Improving concurrency by setting registry variables

DB2 allows you to defer row locks for cursor stability (CS) or read stability (RS) isolation scans in certain cases. This deferral can last until a record is known to satisfy the predicates of a query when row locking is performed during a table or index scan.

To improve concurrency, deferring row locking until after determining that a row qualifies for a query might be possible. Usually, concurrency is improved by setting the registry variables DB2\_SKIPDELETED to permit scans to unconditionally skip uncommitted deletes, and DB2\_SKIPINSERTED to permit scans to unconditionally skip uncommitted inserts. Example 4-4 shows how to enable these two registry variables for the MONITOR database.

Example 4-4 Enabling registry values DB2\_SKIPDELETED and DB2\_SKIPINSERTED

db2 connect to MONITOR db2set DB2\_SKIPDELETED=ON db2set DB2\_SKIPINSERTED=ON

#### **Avoiding full transaction log**

DB2 Health Monitor (HMON) regularly captures information about the database manager, database, table spaces, and tables. It calculates health indicators based on data retrieved from database system monitor elements, the operating system, and the DB2 system. Transactions hang if HMON examines the status for the following table and the transaction occupies the entire transaction log, resulting in an error with SQLCODE 964:

<MONMEBUS SCHEMA>.SIBOWNER

To prevent this error, you can disable the HMON process by using the following command: db2 update dbm cfg using HEALTH MON OFF

#### Setting lock timeout properly

The LOCKTIMEOUT parameter specifies the number of seconds that an application waits to obtain a lock. This parameter helps avoid global deadlocks for applications. If you set this parameter to 0 (zero), the application does not wait for locks. In this situation, if the lock is unavailable at the time of the request, the application immediately receives a -911 return code.

If you set this parameter to -1, lock timeout detection is turned off.

A value of 30 seconds might be a good starting value; tune as necessary after setting this value. The following example shows how to set this parameter for the MONITOR database.

Example 4-5 Starting value for LOCKTIMEOUT

db2 -v update db cfg for MONITOR using LOCKTIMEOUT 30

#### Limiting event XML to 32 KB where possible

Events that are small enough are persisted to a regular VARCHAR column in the incoming events table; large events are persisted to a binary large object (BLOB) column instead. In DB2, the largest VARCHAR column is 32768 bytes. Performance improves considerably when a VARCHAR column is used instead of a BLOB.

#### Using materialized query tables

When you have a deep history of data (for example, more than 10 million Monitoring Context instances), the response time for dashboard navigation in dimensional reports can degrade significantly. IBM Business Monitor V8.0 uses Cognos Business Intelligence V10.1.1 for its dimensional reports. Business Monitor provides a tool that can be used with DB2 to generate cube summary tables that pre-compute the values of measures for known dimensional member values. Such values include the value of the "average loan amount" measure based on values for the "customer loyalty level" dimension, say, for bronze, silver, and gold customers. DB2 calls these tables *materialized query tables*, and Business Monitor provides a scheduled service to refresh them on a periodic basis.

For details about using this capability, see the following information center topic:

http://publib.boulder.ibm.com/infocenter/dmndhelp/v7r5mx/index.jsp?topic=/com.ibm.wbpm.mon.admin.doc/data/enable\_cubesumtable\_refresh.html

# 4.15 Oracle-specific database tuning

As with DB2, providing a comprehensive Oracle database tuning guide is beyond the scope of this paper. However, several guidelines can assist in helping you improve the performance of Business Process Manager products when used in Oracle environments. This section describes the and provides pointers to more detailed information. In addition, the following references are useful:

- Oracle Database 11g Release 1 documentation (includes a performance tuning guide): http://www.oracle.com/pls/db111/homepage
- Oracle Architecture and Tuning on AIX v2.20 white paper: http://www.ibm.com/support/techdocs/atsmastr.nsf/WebIndex/WP100883

# 4.15.1 Updating database statistics

Oracle provides an automatic statistics-gathering facility, which is enabled by default. One approach for updating statistics manually on all tables in a schema is to use the dbms\_stats utility. For more information, see the Oracle product documentation.

# 4.15.2 Correctly setting buffer cache sizes

Oracle provides automatic memory management for buffer caches. For more information about configuring automatic memory management and for guidance on manually setting buffer cache sizes, see the following references:

- ► For Oracle 10g R2
  http://download.oracle.com/docs/cd/B19306\_01/server.102/b14211/memory.htm#i29118
- ► For Oracle 11g R1
  http://download.oracle.com/docs/cd/B28359\_01/server.111/b28274/memory.htm#i29118

## 4.15.3 Maintaining correct table indexing

The SQL Access Advisor, available from the Enterprise Manager, provides suggestions for schema changes, including changes to indexes. You can find the SQL Access Advisor by starting at the database home page, then following the Advisor Central link in the Related Links section at the bottom of the page.

In our internal evaluation, we found that the following indexes are often helpful for BPMN business processes. Consider these indexes as a starting point for defining indexes, and add more indexes as described previously.

- create index PS.TASK BIS on PS.LSW TASK("BPD INSTANCE ID", "STATUS");
- create index PDW.TASK IDS on PDW.LSW TASK("SYSTEM ID", "SYSTEM TASK ID");
- create index PS.TASK UGI on PS.LSW TASK("USER ID","GROUP ID","TASK ID");
- create index PS.TASK\_UI on PS.LSW\_TASK("USER\_ID","TASK\_ID");

## 4.15.4 Sizing log files appropriately

Unlike DB2, Oracle performs an expensive checkpoint operation when switching logs. The checkpoint involves writing all dirty pages in the buffer cache to disk. Therefore, an important steps is to make the log files large enough that switching occurs infrequently. Applications that generate a high volume of log traffic need larger log files to achieve this goal.

## 4.15.5 Using the Oracle SQL Tuning Advisor for long running SQL statements

If analysis shows that a particular SQL statement is taking a long time to execute, it might be because the Oracle database is executing the SQL in a non-optimal manner. The Oracle SQL Tuning Advisor can be used to optimize the performance of long running SQL statements. Use the following methodology to identify, and improve, the performance of these SQL statements:

- Identify long-running SQL statements by using an AWR report, or through the Event Manager.
- ▶ Run the SQL Tuning Advisor against the long-running SQL statements.
- Evaluate and accept (as is appropriate) the recommendations from the SQL Tuning Advisor.

# 4.15.6 File system tuning

For redo logs and control files on AIX, use a file system with agblksize parameter set to 512. For other file systems, use the default agblksize.

# 4.15.7 Creating table spaces

When creating table spaces, consider minimizing the number of table space expansions (extends) that occur by setting large initial and autoextend sizes. This step can help produce fewer spikes in database utilization under peak load.

Alternatively, manually extend the table spaces during periods of relatively low activity to mitigate this issue.

## 4.15.8 Special considerations for large objects (LOBs)

Business Process Manager workloads often use LOBs to store data. For Oracle databases, LOBs are most efficiently handled by using the file system cache, while other database activity is more efficiently managed by using concurrent I/O. So, to achieve optimal performance, the LOBs must be managed separately from other I/O activity. Use the following approach to achieve this performance:

- ▶ Disable concurrent I/O at the database level. For example, for AIX set filesystemio\_options to asynch.
- ▶ Move the LOBs to separate file systems.
- ▶ Mount all file systems that do *not* have LOBs using concurrent I/O.
- Partition the LOB table spaces to reduce file locking contention.

Also for LOBs, enable caching for LOB columns for the lsw\_task\_execution\_context and lsw\_bpd\_instance\_data tables

## 4.15.9 Setting prepared statement cache size

Prepared statements that are cached perform faster than those not cached. However, for Oracle databases, each prepared statement can take a significant amount of Java heap space (140 KB per statement for some cases that we have seen in Business Process Manager solutions). As such, do the following tasks:

- ▶ Judiciously set prepared statement cache sizes to be large enough to improve performance (particularly for the BPEDB data source for BPEL business processes, which realize significant benefit from the prepared statement cache).
- Monitor Java heap utilization to ensure that the prepared statements are not using too much heap space or causing OutOfMemory exceptions.

## 4.15.10 Specific tuning parameter recommendations

For our internal performance evaluation of the Business Process Manager 8.0 Process Server, we changed the following Oracle database settings from their default. This approach is a useful starting point for tuning the Oracle database, but follow the suggested methodology for your applications and configuration. The first four settings in the following list generally vary by workload and volume, so consult with your database administrator to determine appropriate values. Also, the last two settings work well for Business Process Manager solutions where the Oracle undo operation is typically not used, but might not work well for non-Business Process Manager databases.

memory\_max\_target: 25G

memory\_target: 25G

► processes: 500

open\_cursors: 1000

▶ undo retention: 200

▶ undo autotune: FALSE

Also, edit the 98database.xml file in the profiles configuration directory, and change the following parameter to keep more threads active in the connection pool to better manage peak throughput.

<max-idle>40</max-idle>

# 4.15.11 Suggestions for Business Process Execution Language business processes

Web material is available that offers suggestions for tuning BPEL business processes in Business Process Manager V8.0.

The following website explains how to specify initial Oracle database settings:

http://publib.boulder.ibm.com/infocenter/dmndhelp/v7r0mx/index.jsp?topic=/com.ibm.websphere.bpc.doc/doc/bpc/t5tuneint spec init db oracle.html

The following website explains how to create an Oracle database for Business Process Choreographer. It provides details about BPEDB creation, including pointers to useful creation scripts for a production environment:

http://publib.boulder.ibm.com/infocenter/dmndhelp/v7r0mx/index.jsp?topic=/com.ibm.
websphere.bpc.doc/doc/bpc/t2codbdb.html

The default Oracle policy for LOBs is to store the data within the row when the size of the object does not exceed a threshold. In some cases, workloads have LOBs that regularly exceed this threshold. By default, such LOB accesses bypass the buffer cache, meaning that LOB read operations are exposed to disk I/O latencies when using the preferred direct or concurrent path to storage.

# 4.16 Advanced Java heap tuning

Because the Business Process Manager product set is written in Java, the performance of the JVM has a significant impact on the performance delivered by these products. JVMs externalize multiple tuning parameters that might be used to improve both authoring and runtime performance. The most important of these parameters are related to garbage collection and setting the Java heap size. This section explains these topics in detail.

The products covered in this paper use IBM JVMs on most platforms (for example, AIX, Linux, and Windows), and the HotSpot JVMs on selected other systems, such as Solaris. Business Process Manager 8.0 uses Java 6. It has characteristics similar to Java 5, which is used in Business Process Manager V6.1 and V6.2.0 products but is much different from Java 1.4.2 that used by Business Process Manager V6.0.2.x and earlier versions. For brevity, only Java 6 tuning is described here.

The IBM Java 6 diagnostics guide is at the following website:

http://publib.boulder.ibm.com/infocenter/javasdk/v6r0/index.jsp

The guide describes many more tuning parameters than those described in this paper, but most are for specific situations and are not of general use. For a more detailed description of IBM Java 6 garbage collection algorithms, see the section on memory management.

The following sites contain additional Oracle HotSpot JVM references:

- Summary of HotSpot JVM options for Solaris
  - http://java.sun.com/docs/hotspot/VMOptions.html
- ► FAQs about the Solaris HotSpot JVM
  - http://java.sun.com/docs/hotspot/PerformanceFAQ.html#20
- Additional tuning information for Oracle HotSpot JVM http://java.sun.com/docs/performance/

## 4.16.1 Monitoring garbage collection

To set the heap correctly, determine how the heap is being used by collecting a verbosegc trace. A verbose garbage collection (verbosegc) trace prints garbage collection actions and statistics to stderr in IBM JVMs and stdout in Oracle HotSpot JVMs. The verbosegc trace is activated by using the Java runtime option -verbose:gc. Output from verbosegc differs for the HotSpot and IBM JVMs, as shown by Example 4-6 and Example 4-7.

Example 4-6 IBM JVM verbosegc trace output

```
<af type="tenured" id="12" timestamp="Fri Jan 18 15:46:15 2008" intervalms="86.539">
 <minimum requested bytes="3498704" />
  <time exclusiveaccessms="0.103" />
  <tenured freebytes="80200400" totalbytes="268435456" percent="29" >
   <soa freebytes="76787560" totalbytes="255013888" percent="30" />
   <loa freebytes="3412840" totalbytes="13421568" percent="25" />
  </tenured>
  <gc type="global" id="12" totalid="12" intervalms="87.124">
    <refs cleared soft="2" threshold="32" weak="0" phantom="0" />
   <finalization objectsqueued="0" />
   <timesms mark="242.029" sweep="14.348" compact="0.000" total="256.598" />
   <tenured freebytes="95436688" totalbytes="268435456" percent="35" >
     <soa freebytes="87135192" totalbytes="252329472" percent="34" />
     <loa freebytes="8301496" totalbytes="16105984" percent="51" />
   </tenured>
 </gc>
  <tenured freebytes="91937984" totalbytes="268435456" percent="34" >
   <soa freebytes="87135192" totalbytes="252329472" percent="34" />
   <loa freebytes="4802792" totalbytes="16105984" percent="29" />
 </tenured>
  <time totalms="263.195" />
</af>
```

Example 4-7 Solaris HotSpot JVM verbosgc trace output (young and old)

```
[GC 325816K \rightarrow 83372K(776768K), 0.2454258 secs]
[Full GC 267628K \rightarrow 83769K <- live data (776768K), 1.8479984 secs]
```

Oracle HotSpot JVM verbosegc output can be more detailed by setting additional options:

- ► -XX:+PrintGCDetails
- ► -XX:+PrintGCTimeStamps

Parsing the verbosegc output by using a text editor can be tedious. Visualization tools that can be used for more effective Java heap analysis are available on the web. The IBM Pattern Modeling and Analysis Tool for Java Garbage Collector (PMAT) is one such tool. It is available for download at IBM alphaWorks® at the following website:

http://www.alphaworks.ibm.com/tech/pmat

PMAT supports the verbosegc output formats of JVMs offered by major JVM vendors such as IBM, Oracle, and HP.

## 4.16.2 Setting the heap size for most configurations

This section contains guidelines for determining the appropriate Java heap size for most configurations. If your configuration requires that more than one JVM run concurrently on the same system, see 4.16.3, "Setting the heap size when running multiple JVMs on one system" on page 94. For example, you might need more than one JVM if you run both a Business Process Manager server and Integration Designer on the same system. If your objective is designed to support large business objects, read 4.7.2, "Tuning for large objects" on page 63.

When the heap size is too low, OutOfMemory errors occur. For most production applications, the IBM JVM Java heap size defaults are too small, so increase them. When the heap size is too low, OutOfMemory errors occur. In general, the HotSpot JVM default heap and nursery size are also too small so increase them also.

There are several approaches to setting optimal heap sizes. Here we describe the approach that most applications can use when running the IBM JVM on AIX. The essentials can be applied to other systems. Set the initial heap size (-Xms option) to a typical value (for example, 768 MB on a 64-bit JVM, or 256 MB on a 32-bit JVM). Set the maximum heap size (-Xmx) option to a typical value, but large (for example, 3072 MB on a 64-bit JVM, or 1024 MB on a 32-bit JVM). The maximum heap size must never force the heap to page. The heap *must always stay* in physical memory. The JVM then tries to keep the GC time within reasonable limits by growing and shrinking the heap. The output from verbosegc is used to monitor garbage collection (GC) activity.

If Generational Concurrent GC is used (-Xgcpolicy:gencon), you can also set the new area size to specific values. By default, the new size is a quarter of the total heap size or 64 MB, whichever is smaller. For better performance, set the nursery size to half of the heap size or larger, and do not cap the value at 64 MB. You can set new area sizes by using the following JVM options:

- ► -Xmn<size>
- ► -Xmns<initialSize>
- ► -Xmnx<maxSize>

You can use a similar process to set the size of HotSpot heaps. In addition to setting the minimum and maximum heap size, also increase the nursery size to a range of 1/4 to 1/2 of the heap size. Never increase the nursery to more than half the full heap.

You can set the nursery size by using the MaxNewSize and NewSize parameters:

- ► -XX:MaxNewSize=128m
- ► -XX:NewSize=128m

If you are using a 64-bit IBM JVM, use the -Xgc:preferredHeapBase parameter to avoid native out-of-memory issues because of exhaustion of memory addresses below 4 GB (for example, classes and threads are allocated in this region). The -Xgc:preferredHeapBase option can be used to move the Java heap outside of the lower 4 GB address space. See the IBM JVM information center for a more detailed description of the solution:

http://ibm.co/10CGjeT

After the heap sizes are set, use verbosegc traces to monitor GC activity. After analyzing the output, modify the heap settings accordingly. For example, if the percentage of time in GC is high and the heap has grown to its maximum size, you might improve throughput by increasing the maximum heap size. As a general guideline, greater than 10% of the total time spent in GC is generally considered high.

Increasing the maximum size of the Java heap might not always solve this type of problem because the problem might be memory overuse. Conversely, if response times are too long because of GC pause times, decrease the heap size. If both problems are observed, an analysis of the application heap usage is required.

## 4.16.3 Setting the heap size when running multiple JVMs on one system

Each running Java program has a heap associated with it. If you have a configuration where more than one Java program is running on a single physical system, setting the heap sizes appropriately is of particular importance. Setting the heap size is also important for 32-bit systems, where the total amount of addressable memory is limited.

An example of one such configuration is when the Integration Designer is on the same physical system as a Business Process Manager server using a 32-bit JVM. Each of these applications is a separate Java program that has its own Java heap. If the sum of all of the virtual memory usage (including both Java heaps and all other virtual memory allocations) exceeds the size of addressable physical memory, the Java heaps are subject to paging. Such paging causes total system performance to degrade significantly. To minimize the possibility of total system degradation, use the following guidelines:

- ► First, collect a verbosegc trace for each running JVM.
- ▶ Based on the verbosegc trace output, set the initial heap size to a relatively low value. For example, assume that the verbosegc trace output shows that the heap size grows quickly to 256 MB, and then grows more slowly to 400 MB and stabilizes at that point. Based on this change, set the initial heap size to 256 MB (-Xms256m).
- ► Also based on the verbosegc trace output, set the maximum heap size appropriately. Be careful not to set this value too low, or out-of-memory errors occur. The maximum heap size must be large enough to allow for peak throughput. Using the same example, a maximum heap size of 768 MB might be appropriate (-Xmx768m). Correct sizing of maximum heap gives the Java heap room to expand beyond its current size of 400 MB, if required. The Java heap grows only if required (for example, if a period of peak activity drives a higher throughput rate), so setting the maximum heap size higher than current requirements is generally a good policy.
- Be careful not to set the heap sizes too low, or garbage collections will occur frequently, which might reduce throughput. Again, a verbosegc trace assists in determining garbage collection frequency. You must ensure that the heap sizes are large enough that garbage collections do not occur too often. At the same time, you must still ensure that the heap sizes are not cumulatively so large as to cause the heap to page to the file system. This balancing act is depends on configuration.

# 4.16.4 Reducing or increasing heap size if OutOfMemory errors occur

The java.lang.OutOfMemory exception is used by the JVM in various circumstances, so that finding the source of the exception is difficult. There is no conclusive mechanism for telling the difference between these potential error sources, but a good start is to collect a trace using verbosegc. If the problem is a lack of memory in the heap, you can easily see this condition in the output. For more information about verbosegc output, see 4.16.1, "Monitoring garbage collection" on page 92. Many garbage collections that produce little free heap space generally occur preceding this exception. If this lack of free heap space is the problem, increase the size of the heap.

If there is enough free memory when the java.lang.OutOfMemory exception occurs, the next item to check is the finalizer count from the verbosegc (only the IBM JVM provides this information). If this count appears high, a subtle effect might be occurring whereby resources

outside the heap are held by objects within the heap and being cleaned by finalizers. Reducing the size of the heap can alleviate this situation by increasing the frequency with which finalizers are run. In addition, examine your application to determine whether the finalizers can be avoided or minimized.

Out-of-memory errors can also occur for issues unrelated to JVM heap usage, such as running out of certain system resources. Examples of this problem include insufficient file handles or thread stack sizes that are too small.

In some cases, you can tune the configuration to avoid running out of native heap. Try reducing the stack size for threads (the -Xss parameter). Deeply nested methods might force a thread stack overflow if there is insufficient stack size.

Also, if you are using a 64-bit IBM JVM, use the -Xgc:preferredHeapBase parameter to avoid native out-of-memory issues because of exhaustion of memory addresses below 4 GB (for example, classes and threads are allocated in this region).

You can use the -Xgc:preferredHeapBase option to move the Java heap outside of the lower 4 GB address space. See the IBM JVM information center for a more detailed description of the solution:

http://ibm.co/10CGjeT

For middleware products, if you are using an in-process version of the JDBC driver, it is possible to find an out-of-process driver that can have a significant effect on the native memory requirements. For example, you can use type 4 JDBC drivers (DB2 Net drivers or Oracle's Thin drivers), or you can switch IBM MQSeries® from Bindings mode to Client mode. See documentation for DB2, Oracle, and MQSeries for more details.

# 4.17 Tuning for WebSphere InterChange Server migrated workloads

The following tuning suggestions are unique to workloads that are migrated by using the WebSphere InterChange Server migration wizard in the Integration Designer. In addition to these suggestions, see the other Business Process Manager server tuning suggestions detailed in this document:

- ► For JMS-based messaging used to communicate with older WebSphere Business Integration adapters or custom adapters, use non-persistent queues when possible.
- ► For JMS-based messaging used to communicate with older WebSphere Business Integration adapters or custom adapters, use WebSphere MQ-based queues, if available. By default, the adapters use the WebSphere MQ APIs to connect to the service integration bus destinations through MQ Link. MQ Link is a protocol translation layer that converts messages to and from MQ-based clients. By switching to WebSphere MQ-based queues, MQLink translation costs are eliminated and performance is improved.
- Turn off server logs for verbose workloads. Some workloads emit log entries for every transaction, causing constant disk writes and reducing overall throughput. Turning off server logs might reduce the throughput degradation for such workloads.

## **Initial configuration settings**

This chapter suggests initial settings for several relevant parameters. These values are not optimal in all cases, but the values work well in internal IBM performance evaluations. They are, at a minimum, useful starting points for many proof-of-concepts and customer deployments. As described in 4.1, "Performance tuning methodology" on page 48, tuning is an iterative process. Follow that procedure and adjust these values as appropriate for your environment.

#### 5.1 Business Process Manager server settings

This section provides settings based on IBM internal performance evaluations of the Business Process Manager V8.0 server. These settings were derived by using the tuning methodology and guidelines described in Chapter 4, "Performance tuning and configuration" on page 47. Consider these settings useful starting points for your use of this product. For settings that are not listed, use the default settings that are supplied by the product installer as a starting point, and then follow the tuning methodology specified in 4.1, "Performance tuning methodology" on page 48.

Three settings are described in this section:

- ► A three-tiered configuration for Business Process Execution Language (BPEL) business processes, with the production database on a separate server.
- ► A three-tiered configuration for Business Processing Modeling Notation (BPMN) business processes, with the production database on a separate server.
- ► A two-tiered (client/server) configuration for BPEL business processes, with the production database collocated on the server.

# 5.1.1 Three-tiered: Using BPEL business processes with web services and remote DB2 system

Through the WebSphere Application Server, we used a three-tiered configuration in our internal performance work to evaluate the performance of a BPEL business process that models automobile insurance claims processing. This configuration is an example of many production environments where DB2 is on a separate system than the Business Process Manager server. The web services binding was used for communications. The business process has two modes of operation:

- ► A BPEL microflow (straight-through process) that processes claims where no human intervention is required
- ► A BPEL microflow plus macroflow (long-running process) pattern, where the macroflow is started when a review or approval is required (for example, if the claim amount is above a certain limit)

Three systems were used in this configuration:

- ▶ Request driver
- ► Business Process Manager V8.0 server
- ► DB2 database server

The Business Process Manager server and the DB2 database server required extensive tuning to maximize throughput. Some tuning varied because of the operating system (such as AIX and Windows) and the number of processor cores. These variations are presented in tabular format, after the description of common tuning.

For all topologies in this section, we suggest you complete the following actions to tune Business Process Manager and DB2 and maximize throughput:

- ▶ Use the production template.
- Define the Common database as local DB2 type 4.
- ► Establish BPEL Business Process support with bpeconfig.jacl. Click Data sources → BPEDataSourceDb2 → WebSphere Application Server data source properties statement cache to 300.

- ► Disable PMI.
- Set HTTP maxPersistentRequests to -1.
   Set GC policy to -Xgcpolicy:gencon (see Table 5-1 and Table 5-2 for nursery setting -Xmn).
- Use remote DB2 databases (connection type 4) for the SIB System, BPCDB, and SIB BPEDB.

Table 5-1 lists Business Process Manager server-related settings to modify from their default value when the Business Process Manager server is deployed on AIX.

Table 5-1 Three-tiered application cluster settings for AIX

Setting	Value
Java heap Megabytes	1536
Java nursery Megabytes -Xmn	768
Default thread pool max	100
BPEDB Data source → connection pool max	300
BPEDB Data source → WebSphere Application Server data source properties → Statement cache size	300
BPC messaging engine data source → connection pool max	50
SCA SYSTEM messaging engine data source → connection pool max	50
BPM Common Data source → connection pool max	500
J2C activation specifications $\rightarrow$ SOABenchBPELMod2_AS $\rightarrow$ Custom properties $\rightarrow$ maxConcurrency, maxBatchSize	50
Resources → Asynchronous Beans → Work Managers → BPENavigationWorkManager → Work request queue size, max threads, growable	400, 50, no
Application Cluster → Business Flow Manager → Message pool size, Intertransaction cache size	5000, 400
WebContainer thread pool min, max	100, 100
com.ibm.websphere.webservices.http.maxConnection	50

Table 5-2 lists Business Process Manager server-related settings to modify from their default value when Business Process Manager server is deployed on Windows and Linux on Intel systems.

Table 5-2 Three-tiered web service and remote DB2 tuning variations for Windows and Linux on Intel systems

Tuning variations	Microflow: Number of cores			Macroflow: Number of cores	
	1	2	4	1	4
Java heap Megabytes	1280	1280	1280	1280	1280
Java nursery Megabytes -Xmn	640	640	640	768	768
Web container thread pool max	100	150	150	100	300
Default thread pool max	100	200	200	100	200

Tuning variations	Microflow	: Number of cor	Macroflow: N	Macroflow: Number of cores	
	1	2	4	1	4
BPE database connection pool max	150	250	250	150	350
BPC messaging engine database connection pool max	30	30	30	30	150
SYSTEM messaging engine database connection pool max	30	40	40	30	100
Common database connection pool max	80	80	80	80	100
J2C activation specifications → SOABenchBPELMod2_AS → Custom properties → maxConcurrency	40	40	40	160	160
BPEInternalActivationSpec batch size				10	10
SOABenchBPELMod2_AS batch size				32	32
Java custom property com.ibm.websphere.webservic es.http.maxConnection	100	200	200	200	200
Application servers → server1 → Business Flow Manager → allowPerformanceOptimizations				Yes	Yes
Application servers → server1 → Business Flow Manager → interTransactionCache.size				400	400
Application servers → server1 → Business Flow Manager → workManagerNavigation.messa gePoolSize				4000	4000
Resources → Asynchronous Beans → Work Managers → BPENavigationWorkManager → min threads, max threads, request queue size				30, 30, 30	30, 30, 30

The DB2 database server has several databases that are defined for use by the Business Process Manager server. Spread the database logs and table spaces across a RAID array to distribute disk use. Tune the SCA.SYSTEM.<a href="mailto:scellname">scellname</a>. BUS database and the BPEDB as follows:

- ▶ db2 update db cfg for sysdb using logbufsz 512 logfilsiz 8000 logprimary 20 logsecond 20 auto runstats off
- ▶ db2 alter bufferpool ibmdefaultbp size 30000

Create and tune the BPE database by using the following DB2 commands and generated scripts:

- ▶ db2 CREATE DATABASE bpedb ON /raid USING CODESET UTF-8 TERRITORY en-us
- ▶ db2 update db cfg for bpedb using logbufsz 512 logfilsiz 10000 logprimary 20 logsecond 10 auto runstats off
- db2 -tf createTablespace.sql (Business Process Manager V7.5 server generated script)
- db2 -tf createSchema.sql (Business Process Manager V7.5 server generated script)
- ▶ db2 alter bufferpool ibmdefaultbp size 132000
- ▶ db2 alter bufferpool bpebp8k size 132000

#### 5.1.2 Three-tiered: Using Human Services with BPMN business processes

We used a three-tiered configuration in our internal performance work to evaluate the performance of a BPMN business process that models automobile insurance claims processing. Human Services were used to process the claims with a Call Center scenario of Query Tasks, Claim Task, Complete Task, and Commit Task.

This configuration is an example of many production environments where DB2 is on a separate system than the Business Process Manager server. The web services open SCA binding was used for communications. Three systems were used in this configuration:

- Request driver
- ► Business Process Manager V8.0 Process Server
- ► DB2 database server

#### **Business Process Manager Process Server in three-tiered configuration**

Use the following settings for the Business Process Manager V8.0 Process Server in a three-tiered configuration.

- ► For a 64-bit JVM, alter Java memory management settings by adding Java command-line parameters:
  - -Xgencon, -Xms1800M, -Xmx1800M, -Xmn800M
- ▶ Increase size of the WebContainer ThreadPool to a minimum of 200, maximum of 400.
- ▶ Increase the maximum size of the Default Thread Pool to 40.
- Disable logging for selected Business Process Manager Process Server components (for example, web services).
- Set bpd-queue-capacity to 10 times the number of physical processor cores, capped at 80
- ► Set max-thread-pool-size to 30 plus 10 times the number of physical processor cores, capped at 110.

#### DB2 database server in three-tiered configuration

To use the DB2 database server in a three-tiered configuration, the following settings are required:

- Separate log files and containers onto separate (RAID) disks
- ► Increase log file size for twproc database to 16384 pages)
- ► Enable file system caching for twproc database: db2 alter tablespace userspace1 file system caching
- ► Exclude the table SIBOWNER from automatic runstats execution, as described in the following technote:

http://www.ibm.com/support/docview.wss?uid=swg21452323

- Ensure that database statistics are current.
  - If running at high throughput rates, consider disabling some or all database auto-maintenance tasks to avoid impacting peak throughput. However, if you disable these capabilities, be sure to use **runstats** regularly to update database statistics
- ► Use your database vendor's tool to obtain recommendations for indexes to create; this task is necessary because different applications often require unique indexes. Create the indexes that are suggested by the database vendor's tool.

#### 5.1.3 Two-tiered: Using file store for Java Message Service

We used a two-tiered configuration to evaluate the performance of a long-running business process that models a typical mortgage application process. This configuration is used with the Business Process Manager server and DB2 on the same physical system as is common for proofs-of-concept when limited hardware is available. However, the configuration is not a representative production configuration. Java Message Service (JMS) binding is used for communication.

In this configuration, the BPE uses a DB2 database, and the messaging engines are configured to use file stores. To select the file store option, start the Profile Management Tool, click **Advanced Profile Creation**, and in the Database Configuration window, click **Use a file store for Messaging Engines**.

Tuning parameter settings for the BPE database were initially derived using the DB2 Configuration Advisor. The following key parameter settings are modified further:

- MAXAPPLS is enlarged enough to accommodate connections from all possible JDBC Connection Pool threads.
- ► The default buffer pool sizes (number of 4 KB pages in IBMDEFAULTBP) for each database are set so that each pool is 256 MB in size.

Table 5-3 shows the parameter settings that are suggested for this configuration.

Table 5-3 Two-tiered configuration using JMS file store parameter settings

Parameter names	Business Process Choreographer database (BPEDB) settings
APP_CTL_HEAP_SZ	144
APPGROUP_MEM_SZ	13001
CATALOGCACHE_SZ	521
CHNGPGS_THRESH	55
DBHEAP	600
LOCKLIST	500
LOCKTIMEOUT	30
LOGBUFSZ	245
LOGFILSIZ	1024
LOGPRIMARY	11
LOGSECOND	10
MAXAPPLS	90
MAXLOCKS	57
MINCOMMIT	1
NUM_IOCLEANERS	6
NUM_IOSERVERS	10
PCKCACHESZ	915
SOFTMAX	440
SORTHEAP	228
STMTHEAP	2048
DFT_DEGREE	1
DFT_PREFETCH_SZ	32
UTIL_HEAP_SZ	11663
IMBDEFAULTBP	65536

In addition to these database-level parameter settings, you must modify several other parameters by using the administrative console. These settings primarily affect concurrency (thread settings):

- ► The amount of expected concurrency influences the size of the thread pool because more in-flight transactions require more threads. As a possible remedy, you might increase the size of the default thread pool beyond the default of 50 threads.
- Set the maximum concurrency to 50 threads for activation specifications.
- ► For the Business Process Choreographer Database (BPEDB), increase the database connection pool size to 60 and the statement cache size to 300.

- ► Set the Maximum Connections property for JMS connection pools to 40.
- Connect to the local database by using the DB2 JDBC Universal Driver type 2 driver. Type 2 drivers produce better performance when the Business Process Manager V8.0 server and DB2 are on the same physical system.
- ► Set the Business Process Manager V8.0 server JVM heap size to a fixed size of 1024 MB. In addition, use the gencon garbage collection policy.

#### 5.2 Mediation Flow Component settings

This section describes settings used for selected internal performance evaluations of Mediation Flow Components. These settings were derived by using the tuning methodology and guidelines described in Chapter 4, "Performance tuning and configuration" on page 47. Consider these settings starting points for using Mediation Flow Components. For settings that are not listed, use the default settings that are supplied by the product installer as a starting point. See 4.1, "Performance tuning methodology" on page 48 for a description of tuning methodology.

#### 5.2.1 Mediation Flow Component common settings

WebSphere ESB settings are good starting points for tuning a WebSphere ESB solution, regardless of binding choices:

- ► Tracing is disabled.
- ► If security is required, application security instead of Java2 security is used to reduce processor usage.

#### 5.2.2 Mediation Flow Component settings for web services

The WebSphere ESB settings for web services are as follows:

- PMI monitoring is disabled
- ▶ Value of WebContainer thread pool sizes is set to max 50 and min 10
- Value of WebContainer thread pool inactivity timeouts for thread pools is set to 3500

#### 5.2.3 Mediation Flow Component settings for Java Message Service

The WebSphere ESB settings for WebSphere MQ and JMS are as follows:

- Activation specification
  - Set the maximum concurrent endpoints to 50.
- Queue Connection factory
  - Set the maximum connection pool size to 51.
- DiscardableDataBufferSize
  - Set the size to 10 MB and set CachedDataBufferSize to 40 MB.

#### 5.2.4 DB2 settings for Java Message Service persistent

Set the following values. They are relevant only for JMS persistent configurations because they use the database to persist messages:

- ▶ Place database table spaces and logs on a fast disk subsystem.
- ▶ Place logs on separate device from table spaces.
- ► Set buffer pool size correctly.
- ► Set the connection min and max to 30.
- ▶ Set the statement cache size to 40.
- ► Set up a raw partition for DB2 logs.

Otherwise, unless noted in the workload description, use the default settings as supplied by the product installer.

### **Related publications**

The publications listed in this section are considered particularly suitable for a more detailed discussion of the topics covered in this paper.

#### **IBM Redbooks**

For information about ordering this publication, see "How to get Redbooks" on page 108. The document referenced here might be available in softcopy only.

- ▶ IBM Business Process Manager V7.5. Production Topologies, SG24-7976
- ► IBM Operational Decision Management (WODM) V8.0 Performance Tuning Guide, REDP-4899

#### Online resources

These websites are also relevant as further information sources:

- WebSphere Application Server Performance
  - http://www.ibm.com/software/webservers/appserv/was/performance.html
- ► WebSphere Application Server Information Center (including Tuning Guide)
  http://www-306.ibm.com/software/webservers/appserv/was/library/?S CMP=rnav
- ► DB2 Version 9 best practices
  - http://www.ibm.com/developerworks/data/bestpractices/?&S TACT=105AGX11&S CM
- DB2 Version 9.7 Information Center
  - http://publib.boulder.ibm.com/infocenter/db2luw/v9r7/index.jsp
- ▶ Diagnostics Guide for IBM SDK and Runtime Environment Java Technology Edition, Version 6
  - http://publib.boulder.ibm.com/infocenter/javasdk/v6r0/index.jsp
- ▶ IBM Pattern Modeling and Analysis Tool for Java Garbage Collector
  - http://www.alphaworks.ibm.com/tech/pmat
- Oracle 11g Documentation Library
  - http://www.oracle.com/pls/db111/homepage
- ► IBM Business Process Managementv8.0 Information Center
  - http://pic.dhe.ibm.com/infocenter/dmndhelp/v8r0mx/index.jsp?topic=%2Fcom.ibm.wbpm.main.doc%2Fic-homepage-bpm.html
- Performance tuning resources for WebSphere Process Server and IBM Business Process Manager solutions
  - http://www.ibm.com/developerworks/websphere/library/techarticles/1111\_herrmann/1111 herrmann.html

Understanding and Tuning the Event Manager http://www.ibm.com/support/docview.wss?uid=swg21439613

► Best practices for DB2 for Linux, UNIX, and Windows

http://www.ibm.com/developerworks/data/bestpractices/db2luw/

▶ DB2 Version 9.5 Information Center

http://publib.boulder.ibm.com/infocenter/db2luw/v9r5/index.jsp

► Extending a J2CA adapter for use with WebSphere Process Server and WebSphere Enterprise Service Bus

http://www-128.ibm.com/developerworks/library/ws-soa-j2caadapter/index.html?ca= drs-

Oracle 10g Release 2 Documentation Library (including Performance Tuning Guide)
 http://www.oracle.com/pls/db102/homepage

#### How to get Redbooks

You can search for, view, or download Redbooks, Redpapers, technotes, draft publications and Additional materials, and order hardcopy Redbooks publications, at this website:

ibm.com/redbooks

#### **Help from IBM**

IBM Support and downloads

ibm.com/support

**IBM Global Services** 

ibm.com/services



# IBM Business Process Manager V8.0 Performance Tuning and Best Practices



Learn valuable tips for tuning

Get the latest best practices

See example settings

This IBM Redpaper publication provides performance tuning tips and best practices for IBM Business Process Manager V8.0 (all editions) and IBM Business Monitor V8.0. These products represent an integrated development and runtime environment based on a key set of service-oriented architecture (SOA) and business process management technologies. Such technologies include Service Component Architecture (SCA), Service Data Object (SDO), Business Process Execution Language (BPEL) for web services, and Business Processing Modeling Notation (BPMN).

Both IBM Business Process Manager and Business Monitor build on the core capabilities of the IBM WebSphere Application Server infrastructure. As a result, Business Process Manager solutions benefit from tuning, configuration, and best practices information for WebSphere Application Server and the corresponding platform Java virtual machines (JVMs).

This paper targets a wide variety of groups, both within IBM (development, services, technical sales, and others) and customers. For customers who are either considering or are in the early stages of implementing a solution incorporating Business Process Manager and Business Monitor, this document proves a useful reference. The paper is useful both in terms of best practices during application development and deployment and as a reference for setup, tuning, and configuration information.

This paper introduces many issues that influence performance of each product and can serve as a guide for making rational first choices in terms of configuration and performance settings. Similarly, customers who already implemented a solution with these products might use the information presented here to gain insight into how their overall integrated solution performance might be improved.

INTERNATIONAL TECHNICAL SUPPORT ORGANIZATION

BUILDING TECHNICAL INFORMATION BASED ON PRACTICAL EXPERIENCE

IBM Redbooks are developed by the IBM International Technical Support Organization. Experts from IBM, Customers and Partners from around the world create timely technical information based on realistic scenarios. Specific recommendations are provided to help you implement IT solutions more effectively in your environment.

For more information: ibm.com/redbooks

REDP-4935-00